


Hercules System/370, ESA/390, z/Architecture Emulator

Hercules – Messages and Codes

Version 3 Release 07



Contents

Contents	2
Figures.....	4
Tables.....	5
1. Preface	6
1.1 Edition information	6
1.2 What this book is about.....	6
1.3 Who should read this book	6
1.4 What you need to know to understand this book.....	6
1.5 How to use this book.....	6
1.6 Revision Notice	6
1.7 Readers Comments	7
1.8 Legal Advice.....	7
1.9 Trademarks	7
1.10 Acknowledgements	8
2. Related Publications	9
2.1 Hercules Emulator – General Information	9
2.2 Hercules Emulator – Installation Guide	9
2.3 Hercules Emulator – User Reference Guide	9
2.4 Hercules Emulator – Messages and Codes	9
2.5 Hercules Emulator – Reference Summary	9
3. Introduction.....	10
3.1 Overview	10
3.2 Locations.....	10
3.3 Message Format	10
3.4 Function List.....	10
3.5 Message Severity.....	12
3.6 Message Examples.....	13
4. Messages HHCAOnnns - Hercules Automatic Operator	15
5. Messages HHCCAnnns - Communication Adapter Emulation	16
6. Messages HHCCFnns - Configuration File Processing.....	24
7. Messages HHCCPnns - CPU Emulation	44
8. Messages HHCCUnnns - Channel-to-Channel Adapter Emulation	49
9. Messages HHCCUnnns - CCKD Utilities.....	50
9.1 Format of the CCKD utilities messages.....	50
10. Messages HHCDAnnns - DASD Emulation (CKD, CCKD and FBA).....	59
11. Messages HHCDCnns - DASDCOPY Utility	60
12. Messages HHCDGnns - Dyngui.DLL	63
13. Messages HHCDInnns - DASDINIT Utility	65
14. Messages HHCDLnns - DASDLOAD Utility	66
15. Messages HHCDSnns - DASDISUP Utility	98
16. Messages HHCDTnns - DASDCAT Utility.....	103
17. Messages HHCDUnnns - DASD Utilities Common Functions	105
18. Messages HHCHDnns - Hercules Dynamic Loader.....	121
19. Messages HHCHEnnns - HETINIT Utility.....	126

20.	Messages HHCHGnnns - HETGET Utility.....	127
21.	Messages HHCHMnnns - HETMAP Utility.....	128
22.	Messages HHCHTnnns - HTTP Server.....	129
23.	Messages HHCHUnnns - HETUPD Utility.....	132
24.	Messages HHCIFnnns - Network Interface Configuration Handler (hercifc).....	133
25.	Messages HHCINnnns - Hercules Initialization.....	135
26.	Messages HHCLCnnns - LCS Emulation.....	138
27.	Messages HHCLGnnns - System Log Functions.....	144
28.	Messages HHCPNnnns - Control Panel Command Messages.....	147
29.	Messages HH CPRnnns - Printer Emulation.....	153
30.	Messages HHCPUnnns - Card Punch Emulation.....	156
31.	Messages HHCRDnnns - Card Reader Emulation.....	157
32.	Messages HHCSDnnns - Socket Devices Common Functions.....	162
33.	Messages HHCTAnnnns - Tape Device Emulation.....	163
34.	Messages HHCTCnnns - TAPECOPY Utility.....	164
35.	Messages HHCTEnnnns - Terminal Emulation.....	165
36.	Messages HHCTMnnns - TAPEMAP Utility.....	169
37.	Messages HHCTSnnns - TAPESPLT Utility.....	170
38.	Messages HHCTTnnns - TOD Clock and Timer Services.....	171
39.	Messages HHCTUnnns - TUN / TAP Driver Support.....	172
40.	Messages HHCVMnnns - VM / CP Emulation.....	173
	Appendix A. Links.....	175
	Index.....	178

Figures

Figure 1: Sample Messages..... 14

Tables

Table 1: Message Format.....	10
Table 2: Hercules Function List.....	12
Table 3: Message Severity.....	12

1. Preface

1.1 Edition information

This edition applies to the Hercules S/370, ESA/390 and z/Architecture Emulator Release 3.07.0 and to all subsequent versions, releases and modifications until otherwise indicated in new editions. Make sure you are using the correct edition for the level of software you are using.

1.2 What this book is about

This book describes all messages and codes of the Hercules Emulator.

For guidance in operating or debugging Hercules, for a general overview or for guidance in installation of the product, additional manuals are available. Please see Chapter “Related Publications” for more information on these manuals.

Please note that some information can be found in more than one manual. This redundancy is not intended to unnecessarily expand the manuals but should help to find all necessary information in one place.

1.3 Who should read this book

This book is mainly intended for people who are responsible for operating the Hercules Emulator. It serves as a starting point for resolving errors in the Hercules environment.

1.4 What you need to know to understand this book

To understand this book you should be somewhat familiar with the Windows (XP, W2K, W2K3, Vista, W2K8) and/or Linux operating systems. You should also be familiar with the installation and operation of the Hercules Emulator itself.

Last but not least you should be familiar with the hardware and software of IBM mainframe environments and their underlying ideas and concepts, as Hercules emulates IBM mainframe hardware.

1.5 How to use this book

This book is designed as a reference book for all messages and codes of the Hercules Emulator and related products. It is not intended to be read chapter by chapter.

1.6 Revision Notice

Hercules Release:	Version 3 Release 07 Modification 0
Publication Number:	HEMC030700
SoftCopy Name:	HerculesMessagesandCodes
Revision Number:	HEMC030700-02
Date:	March 20, 2011

1.7 Readers Comments

If you like or dislike anything about this book please send an email to the address below. Feel free to comment on any errors or lack of clarity. Please limit your comments on the information in this specific book and also include the "Revision Notice" just above. Thank you for your help.

Send your comments by email to the Hercules-390 discussion group:

hercules-390@yahoogroups.com

1.8 Legal Advice

Hercules implements only the raw S/370, ESA/390, and z/Architecture instruction set, it does not provide any operating system facilities. This means that you need to provide an operating system or standalone program which Hercules can load from an emulated disk or tape device. You will have to write the operating system or standalone program yourself, unless you possess a license from IBM to run one of their operating systems on your PC, or use IBM programs and operating systems which have been placed in the public domain.

NOTE: It is YOUR responsibility to comply with the terms of the license for the operating system you intend to run on the Hercules Emulator.

1.9 Trademarks

The following is a list of trademark acknowledgements and copyright notices of product and company names mentioned in this book. Other product and company names in this book, which are not listed below may be the trademarks or registered trademarks of their respective owners.

- IBM, System/370, ESA/390, z/Architecture, MVS, OS/390, z/OS, VM, VM/ESA, z/VM, VSE, VSE/ESA, z/VSE are trademarks or registered trademarks of International Business Machines Corporation (IBM).
- Windows 95, Windows 98, Windows ME, Windows NT, Windows 2000, Windows XP, Windows Vista, Windows 7, Windows Server 2000, Windows Server 2003, Windows Server 2008, Visual C++ Toolkit 2003, Visual C++ 2005 Express are trademarks of Microsoft Corporation.
- Linux is a trademark owned by Linus Torvalds. The Linux Mark Institute is the exclusive licensor of the Linux trademark on behalf of its owner Linus Torvalds.
- WinPcap is copyrighted by NetGroup, Politecnico di Torino (Italy).
- Cygwin is copyrighted by Red Hat, Inc.
- Vista tn3270 is copyrighted by Tom Brennan Software.
- Pentium, XEON are trademarks or registered trademarks of Intel Corporation.
- Athlon, Opteron are trademarks or registered trademarks of Advanced Micro Devices (AMD), Inc.
- Xmit Manager is copyrighted by Neal Johnston-Ward.
- FLEX-ES is a registered trademark of Fundamental Software, Inc.
- UMX Virtual Mainframe is a registered trademark of UMX Technologies.

1.10 Acknowledgements

The Hercules manuals would not have been possible without the assistance of many people and I would like to thank all those who helped me. In particular I would like to thank:

- The Hercules developers for their documentation on various websites from which I derived a great deal of information.
- Roger Bowler and Fish for proof-reading the manuals.
- Loris Degoianni for allowing me to use parts of the original WinPcap documentation.
- Tom Brennan for allowing me to use parts of his Vista tn3270 documentation.
- My colleagues for working with early previews of the documentation, beginning with just a few pages.
- Mike Cairns for reviewing and editing the manuals.

If anyone feels they have been forgotten on this list please let me know.

Peter Glanzmann

2. Related Publications

2.1 Hercules Emulator – General Information

The Hercules "General Information" manual provides an overview of the ideas and concepts of the Hercules Emulator as well as documentation of the emulators functionality. It explains what Hercules does and does not and helps you decide if the software fits to your needs and if it can fulfill all your requirements.

2.2 Hercules Emulator – Installation Guide

The Hercules "Installation Guide" shows you how to install Hercules and all related optional and required software components under the Microsoft Windows, Linux and Apple Macintosh OS X operating systems.

After going through the installation guide you will have a working emulator environment ready to IPL a S370, S/390 or z/Architecture mainframe operating system.

2.3 Hercules Emulator – User Reference Guide

The Hercules "User Reference" leads you through all aspects of the emulators operation. It provides instruction in the operation of the Hercules Emulator with and without the Windows GUI. The usage details for all Hercules utilities are also covered in this guide.

After reading this manual you should be able to work with Hercules and the Hercules console, create virtual devices, understand backup/restore procedures and general housekeeping within the Hercules environment.

2.4 Hercules Emulator – Messages and Codes

The "Messages and Codes" manual provides a detailed explanation of all Hercules related messages. It is the primary source for troubleshooting and debugging when you experience problems with Hercules.

2.5 Hercules Emulator – Reference Summary

The Hercules "Reference Summary" booklet lists all the system parameters, device definitions, console commands, Hercules utilities etc. along with their arguments.

This booklet is intended as a quick reference guide for experienced users. Consult the Hercules "User Reference Guide" for more detailed and additional information.

3. Introduction

3.1 Overview

This Chapter gives an introduction to the messages and codes of the Hercules Emulator and related tools, as well as the messages written from the various standalone utility programs.

3.2 Locations

All messages are written to the Hercules console (native console as well as the Hercules Windows GUI / Hercules Studio) and to the Hercules log file, if a log file is specified in the startup command.

3.3 Message Format

All Hercules-issued messages have the following format:

H H C m m n n n s text

The following table explains the various parts of the message format:

Part	Explanation
HHC	HHC is the message prefix for Hercules. All Hercules messages will have this prefix.
mm	“mm” specifies the function that issued the message. A detailed list of all functions can be found in section 3.4.
nnn	“nnn” specifies the message number. This number is assigned more or less sequentially.
s	“s” is the message severity. Details can be found in section 3.5.
text	“text” is the actual message text.

Table 1: Message Format

3.4 Function List

The following table presents all the Hercules function prefixes from the messages, along with a short description of the function:

Prefix	Function
AO	Hercules Automatic Operator

Prefix	Function
CA	Communication Adapter Emulation
CF	Configuration File Processing
CP	CPU Emulation
CT	Channel-to-Channel Adapter Emulation
CU	CCKD Utilities
DA	DASD Emulation (CKD, CCKD and FBA
DC	DASDCOPY Utility
DG	Dyngui.DLL
DI	DASDINIT Utility
DL	DASDLOAD Utility
DS	DASDISUP Utility
DT	DASDCAT Utility
DU	DASD Utilities Common Functions
HD	Hercules Dynamic Loader
HE	HETINIT Utility
HG	HETGET Utility
HM	HETMAP Utility
HT	HTTP Server
HU	HETUPD Utility
IF	Network Interface Configuration Handler (hercifc)
IN	Hercules Initialization
LC	LCS Emulation
LG	System Log Functions
PN	Hercules Control Panel Command Messages
PR	Printer Emulation
PU	Card Punch Emulation

Prefix	Function
RD	Card Reader Emulation
SD	Socket Devices Common Functions
TA	Tape Device Emulation
TC	TAPECOPY Utility
TE	Terminal Emulation
TM	TAPEMAP Utility
TS	TAPESPLT Utility
TT	TOD Clock and Timer Services
TU	TUN / TAP Driver Support
VM	VM / CP Emulation Facility

Table 2: Hercules Function List

3.5 Message Severity

The following table shows the different message severities, issued by the Hercules Emulator.

Code	Meaning
S	Severe error. This type of error causes immediate termination of Hercules.
E	Error. The function being executed did not execute correctly but Hercules should continue running
W	Warning. Not necessarily an error but something to take note of and possibly correct.
I	Information. General messages that do not require any further action.
A	Action. You need to do something.
D	Debug. Debugging Messages.

Table 3: Message Severity

3.6 Message Examples

The following figure shows some Hercules messages. Although these messages are from a real IPL, please note that they are not complete i.e some messages have been deleted. The messages are shown just as an example of how messages look, especially the variable parts of messages.

```
01:13:24 Hercules Version 3.05
01:13:24 (c)Copyright 1999-2007 by Roger Bowler, Jan Jaeger, and others
01:13:24 Built on Jun 24 2007 at 07:37:21
01:13:24 Build information:
01:13:24   Win32 (MSVC) build
01:13:24   Modes: S/370 ESA/390 z/Arch
01:13:24   Max CPU Engines: 8
01:13:24   Using fthreads instead of pthreads
01:13:24   Dynamic loading support
01:13:24   Loadable module default base directory is .
01:13:24   Using shared libraries
01:13:24   HTTP Server support
01:13:24   No SIGABEND handler
01:13:24   Regular Expressions support
01:13:24   Automatic Operator support
01:13:24   Machine dependent assists: cmpxchg1 cmpxchg4 cmpxchg8 fetch_dw store_dw
01:13:24   Running on LENA Windows_NT-5.1 i686 MP=2
01:13:24   Crypto module loaded (c) Copyright Bernard van der Helm, 2003-2007
01:13:24   HHCCF020W Vector Facility support not configured
01:13:24   HHCCF065I Hercules: tid=000006AC, pid=1900, pgid=1900, priority=0
01:13:24   HHCTE001I Console connection thread started: tid=00000FBC, pid=1900
01:13:24   HHCTE003I Waiting for console connection on port 3270
01:13:24   HHCDA020I D:/MVS/DASD/WORK00.140c cyls=555 heads=30 tracks=16650 trklen=19456
.
.
01:13:24   HHCDA020I D:/MVS/DASD/TST003.34Bc cyls=560 heads=30 tracks=16800 trklen=19456
01:13:24
01:13:24   HHCCF069I Run-options enabled for this run:
01:13:24     NUMCPU:          2
01:13:24     ASN-and-LX-reuse: DISabled
01:13:24     DIAG8CMD:       DISabled
01:13:24   HHCCP002I CPU0000 thread started: tid=00000820, pid=1900, priority=0
01:13:24   HHCCP003I CPU0000 architecture mode S/370
01:13:24   HHCTT002I Timer thread started: tid=000007A4, pid=1900, priority=-20
01:13:24   HHCCP002I CPU0001 thread started: tid=000008E4, pid=1900, priority=0
01:13:24   HHCCP003I CPU0001 architecture mode S/370
01:13:24   HHCNP001I Control panel thread started: tid=000006AC, pid=1900
01:13:24   HHCHT001I HTTP listener thread started: tid=00000818, pid=1900
01:13:24   HHCHT013I Using HTTPROOT directory "D:\Hercules\html\"
01:13:24   HHCAO001I Hercules Automatic Operator thread started;
01:13:24     tid=00000F58, pri=0, pid=1900
01:13:24   HHCHT006I Waiting for HTTP requests on port 8081
.
.
01:13:34 quit
01:13:34   HHCIN900I Begin Hercules shutdown
01:13:34   HHCIN901I Releasing configuration
01:13:34   HHCAO002I Hercules Automatic Operator thread ended
01:13:34   HHCCP008I CPU0000 thread ended: tid=00000820, pid=1900
01:13:34   HHCCP008I CPU0001 thread ended: tid=000008E4, pid=1900
01:13:34   HHCCF047I Subchannel 0:0000 detached
.
.
01:13:34   HHCCF047I Subchannel 0:000E detached
```

```

01:13:34 HHCTE004I Console connection thread terminated
01:13:34 HHCCD210I          size free  nbr st   reads  writes l2reads   hits
switches
01:13:34 HHCCD212I -----
01:13:34 HHCCD213I [*]      37956  0%   0           0       0       0       0       0
01:13:34 HHCCD215I D:/MVS/DASD/SORT00.130c
01:13:34 HHCCD216I [0]      37956  0%   0 rw       0       0       0
01:13:34 HHCTT003I Timer thread ended
01:13:34 HHCCF047I Subchannel 0:000F detached
.
.
.
01:13:34 HHCCD210I          size free  nbr st   reads  writes l2reads   hits
switches
01:13:34 HHCCD212I -----
01:13:34 HHCCD213I [*]      148260  0%   0           0       0       0       0       0
01:13:34 HHCCD215I D:/MVS/DASD/TST003.34Bc
01:13:34 HHCCD216I [0]      148260  0%   0 rw       0       0       0
01:13:34 HHCCF047I Subchannel 0:0030 detached
01:13:34 HHCCF047I Subchannel 0:0031 detached
01:13:34 HHCIN902I Configuration release complete
01:13:34 HHCIN903I Calling termination routines
01:13:34 HHCHD900I Begin shutdown sequence
01:13:34 HHCHD901I Calling panel_cleanup
01:13:34 HHCHD902I panel_cleanup complete
01:13:34 HHCHD901I Calling console_shutdown
01:13:34 HHCHD902I console_shutdown complete
01:13:34 HHCHD901I Calling hdl_term
01:13:34 HHCHD950I Begin HDL termination sequence
01:13:34 HHCLG014I logger thread terminating
01:13:34 HHCIN099I Hercules terminated

```

Figure 1: Sample Messages

4. Messages HHCAOnnns - Hercules Automatic Operator

HHCAOnnns

Messages HHCAOnnns are not yet documented.

5. Messages HHCCAnnns - Communication Adapter Emulation

HHCCA001I

HHCCA001I CCUU:Connect out to *ipaddr:port* failed during initial status : *System Cause Text*

Explanation

Hercules attempted to make an outgoing TCP connection to *ipaddr:port* but the system indicated that there was an error while processing the request.

System Action

The DIAL or ENABLE CCW that caused the connection attempt ends with Unit Check and Intervention Required. The reason for the failure is indicated in the *System Cause Text* field

Operator Action

None

Programmer Action

Correct the RHOST/RPORT configuration statements in the configuration file. If this message occurred during a program initiated DIAL, correct the dial data.

HHCCA002I

HHCCA002I CCUU:Line Communication thread *thread id* started

Explanation

The thread responsible for asynchronous operations for the BSC emulated line *CCUU* has been started.

System Action

The system continues.

Operator Action

None. This is an informational message.

Programmer Action

None. This is an informational message.

HHCCA003E

HHCCA003E CCUU:Cannot obtain socket for incoming calls : *System Cause Text*

Explanation

A system error occurred while attempting to create a socket to listen for incoming calls.

System Action

The device creation is aborted.

Operator Action

None.

Programmer Action

Check the *System Cause Text* for any information relating to the host system. Notify support.

HHCCA004W**HHCCA004W CCUU:Waiting 5 seconds for port *port* to become available****Explanation**

While attempting to reserve port *port* to listen to, the system indicated the port was already being used.

System Action

The system waits 5 seconds and then retries the operation.

Operator Action

Terminate the device if the port is in error.

Programmer Action

Determine the program holding the specified port. If the port cannot be made available, use a different port.

HHCCA005I**HHCCA005I CCUU:Listening on port *port* for incoming TCP connections****Explanation**

The system is now listening on port *port* for incoming a tcp connection.

System Action

The system continues.

Operator Action

None. This is an informational message.

Programmer Action

None. This is an informational message.

HHCCA006T**HHCCA006T CCUU>Select failed : *System Cause Text*****Explanation**

An error occurred during a 'select' system call.

System Action

The BSC thread is terminated.

Operator Action

None.

Programmer Action

Check the *System Cause Text* for any indication of where the error might come from. Notify Support.

HHCCA007W**HHCCA007W CCUU:Outgoing call failed during ENABLE/DIAL command : System Cause Text****Explanation**

The system reported that a previously initiated TCP connection could not be completed.

System Action

The I/O operation responsible for the TCP outgoing connection is ended with Unit Check and Intervention Required.

Operator Action

If the error indicates that the error is temporary, retry the operation.

Programmer Action

Check that the destination for this line is correctly configured. If the operation was a DIAL attempt, check in the application configuration or operation data.

HHCCA008I**HHCCA008I CCUU:cthread - Incoming Call****Explanation**

The BSC thread has received an incoming call.

System Action

Depending on configuration and operational status, the call is either accepted or rejected. Eventually an ongoing I/O operation may complete.

Operator Action

None. This is an informational message.

Programmer Action

None. This is an informational message.

HHCCA009I**HHCCA009I CCUU:BSC utility thread terminated****Explanation**

The BSC thread has ended.

System Action

The system continues.

Operator Action

Refer to any previous error message to determine if this message was not unexpected.

Programmer Action

Refer to any previous error message to determine if this message was not unexpected.

HHCCA010I**HHCCA010I CCUU:initialization not performed****Explanation**

The Device initialization process has failed.

System Action

The system terminates or continues, depending on the reason for which the device was initialization was initiated.

Operator Action

Refer to any previous error message.

Programmer Action

Refer to any previous error message.

HHCCA011E**HHCCA011E CCUU:Error parsing *Keyword*****Explanation**

The device keyword parser found an error while parsing a known keyword.

System Action

The system continues. The device initialization routine turns on a NOGO flag.

Operator Action

For a runtime initialization, correct the device initialization parameters, otherwise notify the programmer.

Programmer Action

For an engine initialization, correct the device configuration parameters in the configuration file.

HHCCA012E**HHCCA012E CCUU:Unrecognized parameter *Keyword*****Explanation**

The device keyword parser found an unknown keyword in the device parameter list.

System Action

The system continues. The device initialization routine turns on a NOGO flag.

Operator Action

For a runtime initialization, correct the device initialization parameters, otherwise notify the programmer.

Programmer Action

For an engine initialization, correct the device configuration parameters in the configuration file.

HHCCA013E

HHCCA013E CCUU:Incorrect *local port/remote port/local host/remote host specification value*

Explanation

The device initialization routine could not correctly parse a parameter value.

System Action

The system continues. The device initialization routine turns on a NOGO flag.

Operator Action

For a runtime initialization, correct the device initialization parameters, otherwise notify the programmer.

Programmer Action

For an engine initialization, correct the device configuration parameters in the configuration file.

HHCCA014E

HHCCA014E CCUU:Incorrect *switched/dial specification value; defaulting to DIAL=OUT*

Explanation

The device initialization routine found an incorrect DIAL value.

System Action

The system continues. The device initialization routine turns on a NOGO flag.

Operator Action

For a runtime initialization, correct the device initialization parameters, otherwise notify the programmer.

Programmer Action

For an engine initialization, correct the device configuration parameters in the configuration file.

HHCCA015E

HHCCA015E CCUU:Missing parameter : *DIAL=NO/IN/OUT/INOUT and LPORT/RPORT/LHOST/RHOST not specified*

Explanation

The device initialization routine found that a mandatory parameter was not provided for a specific DIAL Value.

System Action

The system continues. The device initialization routine turns on a NOGO flag.

Operator Action

For a runtime initialization, correct the device initialization parameters, otherwise notify the programmer.

Programmer Action

For an engine initialization, correct the device configuration parameters in the configuration file.

Note

For DIAL=NO , LPORT, RPORT and RHOST are needed

For DIAL=IN , LPORT is required

For DIAL=OUT None of LPORT,LHOST,RPORT,RHOST are required
For DIAL=INOUT, LPORT is required

HHCCA016W

HHCCA016W CCUU:Conflicting parameter : DIAL=NO|IN|OUT|INOUT and LPORT|RPORT|LHOST|RHOST=value specified

Explanation

The device initialization routine found that a parameter was provided for a parameter that is not relevant for a specific DIAL value.

System Action

The parameter is ignored. The system continues.

Operator Action

For a runtime initialization, correct the device initialization parameters, otherwise notify the programmer.

Programmer Action

For an engine initialization, correct the device configuration parameters in the configuration file.

Note

For DIAL=IN , RPORT and RHOST are ignored

For DIAL=OUT , LPORT, LHOST, RPORT and RHOST are ignored

For DIAL=INOUT, RPORT and RHOST are ignored

HHCCA017I

HHCCA017I CCUU:LPORT|RPORT|LHOST|RHOST parameter ignored

Explanation

The system indicates that the parameter specified is ignored. This message is preceded by message HHCCA016W.

System Action

The system continues.

Operator Action

None.

Programmer Action

None.

HHCCA018E

HHCCA018E CCUU:Bind failed : *System Cause Text*

Explanation

While attempting to bind a socket to a specific host/port, the host system returned an uncorrectable error.

System Action

BSC Thread terminates.

Operator Action

None.

Programmer Action

Check that the LHOST parameter for this device is indeed a local IP address, otherwise notify support.

HHCCA019E**HHCCA019E CCUU:BSC comm thread did not initialise****Explanation**

The BSC communication thread reported that it terminated while the device was initialising.

System Action

The device is not initialised.

Operator Action

Check for any previously issued error message.

Programmer Action

Check for any previously issued error message.

HHCCA020E**HHCCA020E CCUU:Memory allocation failure for main control block****Explanation**

A memory allocation failure occurred, while attempting to reserve memory for the Communication Adapter control block.

System Action

The device is not initialised.

Operator Action

None.

Programmer Action

Contact support.

HHCCA021I**HHCCA021I CCUU:Initialization failed due to previous errors****Explanation**

The initialization process for device *CCUU* did not complete successfully.

System Action

The device is not initialised.

Operator Action

None.

Programmer Action

Refer to any previous error message.

HHCCA300D**HHCCA300D *Debug Message*****Explanation**

This is a debug message. CCW Tracing has been turned on for this device and the Line Handler issues debug messages to help diagnose interface, conformance and protocol issues.

System Action

The system continues.

Operator Action

If the debug messages are no longer necessary, turn off CCW tracing (panel command : 't-CCUU').

Programmer Action

None.

6. Messages HHCCFnnns - Configuration File Processing

HHCCF001S

HHCCF001S Error reading file *filename* line *lineno*: *error*

Explanation

An error was encountered reading the configuration file named *filename* at line number *lineno*. The error is described by *error*.

Action

Correct the error and restart Hercules.

HHCCF002S

HHCCF002S File *filename* line *lineno* is too long

Explanation

The line at line number *lineno* in the configuration file *filename* is too long and cannot be processed.

Action

Correct the line and restart Hercules.

HHCCF003S

HHCCF003S Cannot open file *filename*: *error*

Explanation

The configuration file named *filename* could not be opened. The error is described by *error*.

Action

Correct the error and restart Hercules.

HHCCF004S

HHCCF004S No device records in file *filename*

Explanation

The configuration file named *filename* does not contain any device definition records. Without these, Hercules cannot do any meaningful work.

Action

Specify one or more device definitions in the configuration file and restart Hercules.

HHCCF005S

HHCCF005S Unrecognized argument *argument*

Explanation

An invalid argument, *argument*, was specified on the HTTPPORT configuration statement in the file named *filename* at line number *lineno*. Only the arguments *auth* and *noauth* are valid.

Action

Correct the invalid argument and restart Hercules.

HHCCF006S

HHCCF006S Error in *filename* line *lineno*: Userid, but no password given *userid*

Explanation

A *userid*, *userid*, was specified on the HTTPPORT configuration statement in the file named *filename* at line number *lineno*, but no password was provided. A password is required if a *userid* is present.

Action

Either remove the *userid*, or specify a password, and restart Hercules.

HHCCF007S

HHCCF007S Error in *filename* line *lineno*: Missing argument

Explanation

The HTTPROOT configuration statement was specified in the file named *filename* at line number *lineno*, but no directory was specified. A directory is required.

Action

Specify the directory where the Hercules web server will find its HTML files and restart Hercules.

HHCCF008E

HHCCF008E Error in *filename* line *lineno*: Unrecognized keyword *keyword*

Explanation

An invalid configuration statement was specified in the file named *filename* at line number *lineno*. The invalid keyword was *keyword*.

Action

Correct the invalid statement and restart Hercules.

HHCCF009S

HHCCF009S Error in *filename* line *lineno*: Incorrect number of operands

Explanation

The configuration statement at line *lineno* of the file named *filename* had an invalid number of operands. For all but the HTTPPORT statement exactly one operand is required.

Action

Correct the invalid statement and restart Hercules.

HHCCF010S

HHCCF010S Error in *filename* line *lineno*: Unknown or unsupported ARCHMODE specification *mode*

Explanation

The ARCHMODE configuration statement at line *lineno* of the file named *filename* specified an invalid architecture. Only S/370, ESA/390, or ESAME are valid. If one of these was specified, then support for that architecture was excluded when the copy of Hercules in use was compiled.

Action

Correct the specified value and restart Hercules. If the message was issued because support for the desired architecture was excluded, then recompile Hercules.

HHCCF011S

HHCCF011S Error in *filename* line *lineno*: *serialno* is not a valid serial number

Explanation

The serial number *serialno* specified on the CPUSERIAL configuration statement at line number *lineno* of the file named *filename* must be exactly six digits long and must be a valid hexadecimal number.

Action

Correct the serial number and restart Hercules.

HHCCF012S

HHCCF012S Error in *filename* line *lineno*: *modelno* is not a valid CPU model

Explanation

The model number *modelno* specified on the CPUMODEL configuration statement at line number *lineno* of the file named *filename* must be exactly four digits long, and must be a valid hexadecimal number.

Action

Correct the model number and restart Hercules.

HHCCF013S

HHCCF013S Error in *filename* line *lineno*: Invalid main storage size *size*

Explanation

The main storage size *size* specified on the MAINSIZE configuration statement at line number *lineno* of the file named *filename* must be a valid decimal number whose value is at least 2. For 32-bit platforms the value must not exceed 4095.

Action

Correct the main storage size and restart Hercules.

HHCCF014S

HHCCF014S Error in *filename* line *lineno*: Invalid expanded storage size *size*

Explanation

The expanded storage size *size* specified on the XPNDSIZE configuration statement at line number *lineno* of the file named *filename* must be a valid decimal number between 0 and 16777215.

Action

Correct the expanded storage size and restart Hercules.

HHCCF015S

HHCCF015S Error in *filename* line *lineno*: Invalid console port number *port*

Explanation

The console port number *port* specified on the CNSLPORT configuration statement at line number *lineno* of the file named *filename* must be a valid nonzero decimal number.

Action

Correct the console port number and restart Hercules.

HHCCF016S

HHCCF016S Error in *filename* line *lineno*: Invalid *threadname* thread priority *priority*

Explanation

The thread priority *priority* specified on the xxxPRIO configuration statement at line number *lineno* of the file named *filename* must be a valid decimal number.

Action

Correct the priority on the statement and restart Hercules.

HHCCF017W

HHCCF017W Hercules is not running as setuid root, cannot raise *threadname* priority

Explanation

A negative value for the *threadname* thread priority parameter *xxxPRIO* was specified but Hercules is not running as the root user (either directly or via the setuid mechanism). This parameter value would cause the priority of the CPU execution thread to be raised above the normal level if Hercules were running as root. Since it is not, however, the parameter will have no effect.

Action

Either specify a positive value to lower the CPU thread priority, zero to not alter the priority, or omit the statement entirely to use the Hercules default CPU thread priority of 15.

HHCCF018S

HHCCF018S Error in *filename* line *lineno*: Invalid number of CPUs *number*

Explanation

The number of emulated CPUs *number* specified on the NUMCPU configuration statement at line number *lineno* of the file named *filename* must be a valid decimal number between 1 and the maximum number defined when Hercules was built (usually 2; this number is never more than 2 for S/370 mode, or 16 for ESA/390 or ESAME mode).

Action

Correct the number of emulated CPUs and restart Hercules.

HHCCF019S

HHCCF019S Error in *filename* line *lineno*: Invalid number of VFs *number*

Explanation

The number of emulated Vector Facility engines *number* specified on the NUMVEC configuration statement at line number *lineno* of the file named *filename* must be a valid decimal number between 1 and the maximum number defined when Hercules was built (usually 2).

Action

Correct the number of emulated Vector Facility engines and restart Hercules.

HHCCF020W

HHCCF020W Vector Facility support not configured

Explanation

A request for Vector Facility support was made by the NUMVEC configuration statement, but Hercules was built without the Vector Facility code. The request has been ignored.

Action

If Vector Facility support is desired, recompile Hercules. If not, remove the NUMVEC configuration statement.

HHCCF021S

HHCCF021S Error in *filename* line *lineno*: Invalid maximum number of CPUs *number*

Explanation

The maximum number of emulated CPUs *number* specified on the MAXCPU configuration statement at line number *lineno* of the file named *filename* must be a valid decimal number. It must not exceed the maximum number (MAX_CPU_ENGINES) defined when Hercules was built.

Action

Correct the MAXCPU parameter and restart Hercules.

HHCCF022S

HHCCF022S Error in *filename* line *lineno*: *epoch* is not a valid system epoch

Explanation

The system epoch *epoch* specified on the SYSEPOCH configuration statement at line number *lineno* of the file named *filename* must be one of the following: 1900, 1928, 1960, 1988, or 1970.

Action

Correct the system epoch and restart Hercules. If a different epoch is desired, a change must be made to the Hercules source file config.c and Hercules rebuilt.

HHCCF023S

HHCCF023S Error in *filename* line *lineno*: *offset* is not a valid timezone offset

Explanation

The system timezone offset *offset* specified on the TZOFFSET configuration statement at line number *lineno* of the file named *filename* must be five characters long and a valid decimal number of the form (+|-)number, where number must be between zero and 2359 (representing 23 hours, 59 minutes).

Action

Correct the time zone offset and restart Hercules.

HHCCF024S

HHCCF024S Error in *filename* line *lineno*: Invalid TOD clock drag factor *drag*

Explanation

The TOD clock drag factor *drag* specified on the TODDRAG configuration statement at line number *lineno* of the file named *filename* must be a valid decimal number between 1 and 10000.

Action

Correct the TOD clock drag factor and restart Hercules.

HHCCF025S

HHCCF025S Error in *filename* line *lineno*: Invalid panel refresh rate *rate*

Explanation

The control panel refresh rate *rate* specified on the PANRATE configuration statement at line number *lineno* of the file named *filename* must be either F, S, or a valid decimal number between 1 and 5000.

Action

Correct the control panel refresh rate and restart Hercules.

HHCCF026S

HHCCF026S Error in *filename* line *lineno*: Unknown OS tailor specification *tailor*

Explanation

The OS tailoring value *tailor* specified on the OSTAILOR configuration statement at line number *lineno* of the file named *filename* must be either OS/390, VSE, VM, LINUX, NULL, or QUIET.

Action

Correct the OS tailoring value and restart Hercules.

HHCCF027S

HHCCF027S Error in *filename* line *lineno*: Invalid maximum device threads *threads*

Explanation

The maximum device threads *threads* specified on the DEVTMAX configuration statement at line number *lineno* of the file named *filename* must be a valid decimal number greater than -1.

Action

Correct the maximum device threads and restart Hercules.

HHCCF028S

HHCCF028S Invalid program product OS permission *permission*

Explanation

The program product OS permission *permission* specified on the PGMPRDOS configuration statement must be either LICENSED or RESTRICTED. The alternative spelling LICENCED is also accepted.

Action

Correct the program product OS permission and restart Hercules.

HHCCF029S

HHCCF029S Invalid HTTP port number *port*

Explanation

The HTTP server port number *port* specified on the HTTPPORT configuration statement must be either 80, or a valid decimal number greater than 1024.

Action

Correct the HTTP server port number and restart Hercules.

HHCCF030S

HHCCF030S Error in *filename* line *lineno*: Invalid I/O delay value *delay*

Explanation

The I/O delay value *delay* specified on the IODELAY configuration statement at line number *lineno* of the file named *filename* must be a valid decimal number.

Action

Correct the I/O delay value and restart Hercules.

HHCCF031S

HHCCF031S Cannot obtain *sizeMB* main storage: *error*

Explanation

An attempt to obtain the amount of main storage specified by MAINSTOR failed for the reason described by *error*.

Action

Correct the error and restart Hercules.

HHCCF032S

HHCCF032S Cannot obtain storage key array: *error*

Explanation

An attempt to obtain storage for the array of storage keys failed for the reason described by *error*.

Action

Correct the error and restart Hercules.

HHCCF033S

HHCCF033S Cannot obtain *sizeMB* expanded storage: *error*

Explanation

An attempt to obtain the amount of expanded storage specified by XPNDSTOR failed for the reason described by *error*.

Action

Correct the error and restart Hercules.

HHCCF034W

HHCCF034W Expanded storage support not installed

Explanation

A request was made for expanded storage by the XPNDSTOR configuration parameter, but Hercules was built without expanded storage support. The request was ignored.

Action

Either remove the XPNDSTOR configuration parameter or recompile Hercules with expanded storage support included.

HHCCF035S

HHCCF035S Error in *filename* line *lineno*: Missing device number or device type

Explanation

The I/O device definition statement at line number *lineno* of the file named *filename* did not contain a device number or a device type.

Action

Supply the missing value and restart Hercules.

HHCCF036S

HHCCF036S Error in *filename* line *lineno*: *number* is not a valid device number(s) specification

Explanation

The I/O device definition statement at line number *lineno* of the file named *filename* specified an invalid device number *number*. The device number must be one to four hexadecimal digits.

Action

Correct the device number and restart Hercules.

HHCCF037S

HHCCF037S Message pipe creation failed: *error*

Explanation

An attempt to create a pipe for communication with the control panel failed. The error is described by *error*.

Action

Correct the error and restart Hercules.

HHCCF038S

HHCCF038S Message pipe open failed: *error*

Explanation

An attempt to open the pipe for communication with the control panel failed. The error is described by *error*.

Action

Correct the error and restart Hercules.

HHCCF039W

HHCCF039W PGMPRDOS LICENSED specified. A licensed program product operating systems is running. You are responsible for meeting all conditions of your software license.

Explanation

The configuration parameter PGMPRDOS LICENSED was specified and Hercules has detected that the operating system is a licensed program product. This message is issued to remind you that compliance with the terms of the license for your system's software is your responsibility.

Action

Be sure you know what you are doing.

HHCCF040E

HHCCF040E Cannot create CPU *number* thread: *error*

Explanation

An attempt to create a new thread for execution of CPU *number* failed. The error is described by *error*. The CPU has not been added to the configuration.

Action

Correct the error and retry the operation.

HHCCF041E

HHCCF041E Device *address* already exists

Explanation

An attempt was made to define a device at address *address*. There is already a device at that address.

Action

Either choose another device address or use the detach command to remove the existing device.

HHCCF042E

HHCCF042E Device type *type* not recognized

Explanation

An attempt was made to define a device of type *type*. This device type is not supported by Hercules. It may also indicate that the system was unable to load the device handler for the specified device type.

Action

Specify a supported device type. If the device type is supported, make sure the the system can load the load modules necessary for device operations. Either use the LD_LIBRARY_PATH environment variable or use ldconfig(8) to customize the library search path.

HHCCF043E

HHCCF043E Cannot obtain device block for device *address*: *error*

Explanation

An attempt to allocate memory for the control block describing the device with address *address* failed. The error is described by *error*. The device has not been defined.

Action

Correct the error and retry the operation.

HHCCF044E

HHCCF044E Initialization failed for device *address*

Explanation

The device at address *address* could not be initialized. The device initialization routine has issued a message describing the problem in further detail; refer to that message for more information.

Action

Correct the error and retry the operation.

HHCCF045E

HHCCF045E Cannot obtain buffer for device *address*: *error*

Explanation

An attempt to allocate memory for the data buffer for the device with address *address* failed. The error is described by *error*. The device has not been defined.

Action

Correct the error and retry the operation.

HHCCF046E

HHCCF046E Device *address* does not exist

Explanation

An attempt was made to remove a device at address *address*. There is no device at that address.

Action

Choose another device address to remove, if desired.

HHCCF047I

HHCCF047I Device *address* detached

Explanation

The device at address *address* has been successfully removed from the system.

Action

None.

HHCCF048E

HHCCF048E Device *address* does not exist

Explanation

An attempt was made to rename a device at address *address*. There is no device at that address.

Action

Choose another device address to rename, if desired.

HHCCF049E

HHCCF049E Device *address* already exists

Explanation

An attempt was made to rename a device to address *address*. There is already a device at that address.

Action

Either choose another device address or use the detach command to remove the existing device.

HHCCF050I**HHCCF050I Device *oldaddr* defined as *newaddr*****Explanation**

The device which was previously defined with the address *oldaddr* has been changed to the address *newaddr*.

Action

None.

HHCCF051S**HHCCF051S Error in *filename* line *lineno*: *verid* is not a valid CPU version code****Explanation**

The version code *verid* specified on the CPUVERID configuration statement at line number *lineno* of the file named *filename* must be exactly two digits long and must be a valid hexadecimal number.

Action

Correct the model number and restart Hercules.

HHCCF052S**HHCCF052S DIAG8CMD invalid option: *option*****Explanation**

The argument *option* on the DIAG8CMD is invalid. Valid options are *enable*, *disable*, *echo*, and *noecho*.

Action

Correct the statement and restart Hercules.

HHCCF053E**HHCCF053E Incorrect second device number in device range near character *c*****Explanation**

The second argument of a device range contains an incorrect device number

Action

Correct the statement and restart Hercules.

HHCCF054E

HHCCF054E Incorrect Device count near character *c*

Explanation

The count field in a device count specification is invalid

Action

Correct the statement and restart Hercules.

HHCCF055E

HHCCF055E Incorrect device address specification near character *c*

Explanation

The first or only CUU in a device specification statement is invalid

Action

Correct the statement and restart Hercules.

HHCCF056E

HHCCF056E Incorrect device address range. *CUU1>CUU2*

Explanation

The first device number of a range is greater than the last device number

Action

Correct the statement and restart Hercules.

HHCCF057E

HHCCF057E *CUU* is on wrong channel (1st device defined on channel *CC*)

Explanation

At least one of the devices in a device number specification is on a different channel than a previously defined device number within the same specification. All device numbers on a single configuration line must be on a single channel (Group of 256 devices)

Action

Correct the statement and restart Hercules.

HHCCF058E

HHCCF058E Some or all devices in *CUU-CUU* duplicate devices already defined

Explanation

At least one of the device numbers on a device specification statement defines a device number that is already specified on that same statement.

Action

Correct the statement and restart Hercules.

HHCCF061W

HHCCF061W ECPS:VM Statement deprecated. Use ECPSVM instead

Explanation

The "ECPS:VM" statement was encountered. This statement is deprecated in favor of the "ECPSVM" statement.

Action

The configuration statement is still carried out but the statement syntax should be changed as soon as possible.

HHCCF062W

HHCCF062W Missing ECPSVM level value. 20 Assumed

Explanation

The "ECPSVM" statement keyword "LEVEL" was encountered but no numeric level followed it.

Action

The default level of 20 is used and the ECPS:VM feature is made available. The statement should be corrected as soon as possible.

HHCCF063W

HHCCF063W Specifying ECPSVM level directly is deprecated. Use the 'LEVEL' keyword instead

Explanation

The deprecated "ECPSVM" level syntax form (without the LEVEL keyword) was found.

Action

The ECPS:VM Level is set to the specified value. The configuration statement should be updated to include the "LEVEL" keyword.

HHCCF064W

HHCCF064W Hercules set priority *priority* failed: *error*

Explanation

An attempt to change the priority of the Hercules process to *priority* failed. The error is described by *error*. The process priority has not been changed. Hercules overall performance may be impaired as a result.

Action

If performance problems are noted, correct the error and restart Hercules.

HHCCF065I

HHCCF065I Hercules: tid=*threadid*, pid=*processid*, pgid=*processgroupid*, priority=*priority*

Explanation

Hercules thread id is *threadid*, its process id is *processid*, its process group id is *processgroupid* and its execution priority is *priority*.

Action

None.

HHCCF066E

HHCCF066E Invalid HTTPROOT: *error*

Explanation

The pathname specified on your HTTPROOT statement is invalid. The error is described by *error*.

Action

Correct the error and restart Hercules.

HHCCF067S

HHCCF067S Incorrect keyword *keyword* for the ASN_AND_LX_REUSE statement

Explanation

The keyword specified for the ASN_AND_LX_REUSE statement is not *ENABLE* or *DISABLE*.

Action

Correct the error and restart Hercules.

HHCCF068E

HHCCF068E Invalid value: *value*; Enter "help scsimount" for help.

Explanation

The automatic SCSI tape mount value is not "NO" nor a value between 1 and 99 seconds inclusive.

Action

Reissue the SCSIMOUNT command.

HHCCF069I

HHCCF069I Run-options enabled for this run:
NUMCPU: n
ASN-and-LX-reuse: Enabled/Disabled
DIAG8CMD: Enabled/Disabled

Explanation

This message confirms the setting of various run-time options specified in the configuration file at startup time.

Action

None.

HHCCF074E

HHCCF074E Unspecified error occurred while parsing Logical Channel Subsystem Identification

Explanation

A logic error occurred while parsing the Logical Channel Subsystem Identification component of a device number or device number group.

Action

Notify Hercules support. This is an error in the Hercules parsing routines.

HHCCF075E

HHCCF075E No more than 1 Logical Channel Subsystem Identification may be specified

Explanation

While specifying a device number or device number group, more than one ':' character was encountered while parsing the Logical Channel Subsystem Identification component. There can be only one Logical Channel Subsystem Identification for a device or group of devices.

Action

Correct the device number or device number group specification and either reissue the command or restart the Hercules engine, depending on whether the error occurred while issuing a command or while starting the engine.

HHCCF076E

HHCCF076E Non numeric Logical Channel Subsystem Identification XX

Explanation

While specifying a device number or device number group, a non-decimal value was encountered while parsing the Logical Channel Subsystem Identification component. The Logical Channel Subsystem Identification for a device or group of devices must be specified as a numeric value.

Action

Correct the device number or device number group specification and either reissue the command or restart the Hercules engine, depending on whether the error occurred while issuing a command or while starting the engine.

HHCCF077E

HHCCF077E Logical Channel Subsystem Identification *NN* exceeds maximum of 3**Explanation**

While specifying a device number or device number group, a Logical Channel Identification was encountered that exceeded the architecture maximum value of *NN*. The Logical Channel Subsystem Identification for a device or group of devices must be within 0 and 3 (inclusive).

Action

Correct the device number or device number group specification and either reissue the command or restart the Hercules engine, depending on whether the error occurred while issuing a command or while starting the engine.

HHCCF079A

HHCCF079A A licensed program product operating system has been detected. All processors have been stopped.**Explanation**

Hercules has detected that the operating system is a licensed program product, but the PGMPRDOS LICENSED parameter was not specified in the Hercules configuration file.

Action

Hercules enters the stopped state. To run this operating system you must obtain a license from the operating system supplier and specify the PGMPRDOS LICENSED parameter in the configuration file. If you are unable to obtain a valid license allowing you to run this operating system on your machine, you must use another operating system (such as MVS 3.8J or Linux for System z) which does not require a license.

HHCCF081I

HHCCF081I *fname* will ignore include errors.**Explanation**

An ignore include_errors statement was encountered in file *fname* requesting that any include statements subsequently found within file *fname* which happen to reference include files which do not exist should simply cause a HHCCF084W warning instead of a HHCCF085S fatal error.

Action

Processing continues. This is an informational-only message.

HHCCF082S

HHCCF082S Error in *fname* line *nnn*: Maximum nesting level (*nn*) reached

Explanation

The maximum number of nested include statements has been exceeded. The include statement which caused the maximum nesting level of *nn* to be exceeded is identified as statement number *nnn* of file *fname*.

Action

This is a fatal error. Configuration file processing is immediately terminated and Hercules startup is aborted. Correct the error and restart Hercules.

HHCCF083I

HHCCF083I *fname1* Including *fname2* at *nnn*.

Explanation

An include statement for file *fname2* was encountered on line *nnn* of file *fname1*.

Action

Configuration file processing switches immediately to processing the statements contained in file *fname2*. Once all of the statements in file *fname2* have been completely processed, configuration file processing will then return to statement *nnn*+1 of file *fname1*. This is an informational-only message.

HHCCF084W

HHCCF084W *fname1* Open error ignored file *fname2*: error

Explanation

File *fname1* contained an include statement for file *fname2* which could not be opened because of error.

Action

Processing continues. This is an informational warning only. Check to make sure the filename specified by *fname2* was spelled correctly and restart Hercules if desired.

HHCCF085S

HHCCF085S *fname1* Open error file *fname2*: error

Explanation

File *fname1* contained an include statement for file *fname2* which could not be opened because of error.

Action

This is a fatal error. Configuration file processing is immediately terminated and Hercules startup is aborted. Correct any misspelling of filename *fname2* and restart Hercules.

HHCCF086S

HHCCF086S Error in *filename*: NUMCPU *nn* must not exceed MAXCPU *mm*

Explanation

The number of online CPUs *nn* specified in the NUMCPU configuration statement in the file named *filename* cannot exceed the maximum number of CPUs *mm* specified in the MAXCPU configuration statement.

Action

Either decrease the NUMCPU parameter, or increase the MAXCPU parameter, and restart Hercules.

HHCCF089S

HHCCF089S Error in *fname* line *linenum*: Invalid log option keyword *val*

Explanation

File *fname* contains an invalid log option keyword *val* on line *num*.

Action

Correct the log option keyword in file *fname* and restart Hercules.

7. Messages HHCCPnnns - CPU Emulation

HHCCP001W

HHCCP001W CPU thread set priority *priority* failed: *error*

Explanation

An attempt to change the priority of the CPU thread to *priority* failed. The error is described by *error*. The thread priority has not been changed. Hercules overall performance may be impaired as a result.

Action

If performance problems are noted, correct the error and restart Hercules.

HHCCP002I

HHCCP002I CPU *number* thread started: tid=*threadid*, pid=*processid*, priority=*priority*

Explanation

The execution thread for CPU number *number* has been started. Its thread id is *threadid*, its process id is *processid* and its execution priority is *priority*.

Action

None.

HHCCP003I

HHCCP003I CPU *number* architecture mode *mode*

Explanation

CPU *number* has been set to the *mode* architecture mode.

Action

If a different architecture mode is desired, it may be changed with the ARCHMODE configuration statement or the archmode control panel command.

HHCCP004I

HHCCP004I CPU *number* Vector Facility online

Explanation

The Vector Facility for CPU *number* is online and available for use.

Action

None.

HHCCP005E

HHCCP005E CPU *number* thread already started

Explanation

An attempt was made to add CPU number *number* to the configuration. This CPU already exists.

Action

If another CPU is desired in the configuration, select a different number.

HHCCP006S

HHCCP006S Cannot create timer thread: *error*

Explanation

An attempt to create the thread used for timing functions has failed. The error is described by *error*. The CPU thread terminates and successful continuation of Hercules is not possible.

Action

Correct the error and restart Hercules.

HHCCP007I

HHCCP007I CPU *number* architecture mode set to *mode*

Explanation

CPU number *number* has been changed to the architecture mode *mode*.

Action

None.

HHCCP008I

HHCCP008I CPU *number* thread ended: tid=*threadid*, pid=*processid*

Explanation

The execution thread for CPU number *number* has ended. Its thread id was *threadid*, and its process id was *processid*.

Action

None.

HHCCP009E

HHCCP009E CPU MASK MISMATCH: *prevmask* - *currmask*. Last instruction: *instruction*.

Explanation

The CPU interrupt mask has changed unexpectedly. The previous mask was *prevmask* and the current mask is *currmask*. The last instruction executed was *instruction*. This is an internal error.

Action

Report this message and the circumstances to the Hercules developers.

HHCCP010I

HHCCP010I CPU *number* store status completed.

Explanation

CPU number *number* has completed a store status operation.

Action

None.

HHCCP011I

HHCCP011I CPU *number*: Disabled wait state

Explanation

CPU number *number* has entered a disabled wait state. It will not execute any further instructions unless it is reset or restarted. This is usually done to report a severe error in execution of an operating system.

Action

Correct the error denoted by the wait state code if applicable.

HHCCP023I

HHCCP023I External interrupt: Interrupt key

Explanation

The CPU has taken an external interrupt because the operator pressed the interrupt key or issued the panel command `ext`.

Action

None.

HHCCP024I

HHCCP024I External interrupt: Clock comparator

Explanation

The CPU has taken a clock comparator interrupt. This message is issued only when the CPU is in single-stepping or instruction-tracing mode.

Action

None. External interrupts are part of normal system operation.

HHCCP025I

HHCCP025I External interrupt: CPU timer=xx...xx

Explanation

The CPU has taken a CPU timer interrupt. xx...xx is the hexadecimal value of the CPU timer. This message is issued only when the CPU is in single-stepping or instruction-tracing mode.

Action

None. External interrupts are part of normal system operation.

HHCCP026I

HHCCP026I External interrupt: Interval timer

Explanation

The CPU has taken an external interrupt caused by the interval timer. This message is issued only when the CPU is in single-stepping or instruction-tracing mode.

Action

None. External interrupts are part of normal system operation.

HHCCP027I

HHCCP027I External interrupt: Service signal *intparm*

Explanation

The CPU has taken a service signal external interrupt. *intparm* is the interrupt parameter. This message is issued only when the CPU is in single-stepping or instruction-tracing mode.

Action

None. External interrupts are part of normal system operation.

HHCCP090W

HHCCP090W The configuration has been placed into a system check-stop state because of an incompatible service call

Explanation

A READ SCP INFO (code X'00020001') Service call has been issued from a CPU which is not a CP engine. All the CPUs in the configuration are put into a Check-Stop state.

Action

Ensure the CPU that issues the service call is a CP engine and restart the program.

8. Messages HHCCTnnns - Channel-to-Channel Adapter Emulation

HHCCTnnns

Messages HHCCTnnns are not yet documented.

9. Messages HHCCUnns - CCKD Utilities

9.1 Format of the CCKD utilities messages

Messages generate by the CCKD utilities are in the format *message_id file message_text*. The format of the message ID is the same as with all other Hercules messages. *file* will either be the part of the file name following the last slash ("/" or "\") when called by a utility command, or will be *xxxx: file[n]* where *xxxx* is the device number and *n* is the shadow file number when called by Hercules.

The *file* portion of the message is omitted in the sections below for brevity.

HHCCU101I

HHCCU101I converting to *endian-format*

Explanation

The file is in the wrong endian (byte order) format for the host architecture. The file is being converted to the host endian format *endian-format*.

Action

None.

HHCCU102I

HHCCU102I compress successful, *n* bytes released

Explanation

The compress function successfully completed and free *n* bytes from the file. If *n* is 0, then the level 2 tables were repositioned to the beginning of the file in order.

Action

None.

HHCCU103I

HHCCU103I file already compressed

Explanation

The compress function determined that the file is already compressed. The file is not updated.

Action

None.

HHCCU104I

HHCCU104I free space rebuilt

Explanation

Free space errors were detected and free space has been successfully rebuilt.

Action

None.

HHCCU300I

HHCCU300I *number space* images recovered

Explanation

Recovery phase 1 completed, recovering *number spaces* (trks or blkgrps).

Action

None.

HHCCU301I

HHCCU301I *space[id]* recovered offset *offset* len *length*

Explanation

The space *space* (trk or blkgrp) was recovered at offset *offset* and length *length*. *id* is the trk or blkgrp number.

Action

None.

HHCCU500W

HHCCU500W recovery not completed, file opened read-only

Explanation

Phase 3 recovery did not complete because the file is not opened for write.

Action

Omit the *-ro* option for *cckdcdisk* or change the file permissions to enable the file to be opened for read-write for Hercules.

HHCCU501W

HHCCU501W recovery not completed, missing compression

Explanation

Phase 3 recovery did not complete because one or more trk or blkgrp images were compressed using a compression (zlib or bzip2) that was not built into Hercules.

Action

Processing terminates. The file has not been updated. Build Hercules with the missing compression libraries.

HHCCU502W

HHCCU502W free space not rebuilt, file opened read-only**Explanation**

Free space errors were detected but the free space was not rebuilt because the file is not opened for write.

Action

Omit the *-ro* option for *cckdcdisk* or change the file permissions to enable the file to be opened for read-write by Hercules.

HHCCU600W

HHCCU600W forcing check level *level*[: *reason*]**Explanation**

Errors have been detected in the compressed file that warrant the escalation of the check level to *level*. An additional explanation *reason* may be supplied.

Action

At a minimum, free space will be rebuilt.

HHCCU601W

HHCCU601W cdevhdr inconsistencies found *code=code***Explanation**

The space statistics in the *cckddasd* device header (*cdevhdr*) contain inconsistencies described by *code*. *code* is a 16-bit bit field and more than one bit may be on. See *cckdutil.c* for the different bit settings.

Action

At a minimum, free space will be rebuilt.

HHCCU602W

HHCCU602W *space* offset *offset len length* is out of bounds**Explanation**

The space *space* (*trk*, *blkgrp* or *l2*) either precedes the end of the L1 table (at the beginning of the file) or exceeds the end of the file.

Action

The space will be recovered. If the space is an L2 table, then all tracks or block groups associated with the table will also be recovered.

HHCCU603W

HHCCU603W *space1* offset *offset1* len *length* overlaps *space2* offset *offset2*

Explanation

The space *space1* overlaps space *space2*.

Action

The spaces will be recovered. If either space is an L2 table, then all tracks or block groups associated with that table will also be recovered.

HHCCU604W

HHCCU604W *space* l2 inconsistency: len *length*, size *size*

Explanation

The space *space* (trk or blkgrp) has an inconsistent l2 entry. Either the length *length* is too small or is too large or exceeds the size *size*.

Action

The space will be recovered.

HHCCU610W

HHCCU610W free space errors detected

Explanation

Free space is not consistent.

Action

Free space will be rebuilt.

HHCCU620W

HHCCU620W *space[id]* hdr error offset *offset*: *xxxxxxxxxx*

Explanation

A header error was found for *space* (trk or blkgrp) during validation. *id* is the trk or blkgrp number. The header is located at file offset *offset*. The contents of the 5 byte header is *xxxxxxxxxx* in hex.

The first byte of the header should be either 00 (compress none), 01 (compress zlib) or 02 (compress bzip2).

For ckd, the next two bytes is the cylinder (in big-endian byte order) and the two bytes after that is the head (also in big-endian byte order).

For fba, the next four bytes is the block group number (in big-endian byte order).

The header contains an invalid value. Either the offset is incorrect or the header has been overlaid.

Action

The space will be recovered.

HHCCU621W

HHCCU621W *space[id]* compressed using *compression*, not supported

Explanation

During validation, the header for *space* (trk or blkgrp) indicates that the space was compressed using *compression* (zlib or bzip2) but support for that compression method was not built into Hercules. *id* is the trk or blkgrp number.

Action

Processing continues. However no recovery will take place. Build Hercules with the specified compression library.

HHCCU622W

HHCCU622W *space[id]* offset *offset* len *length* validation error

Explanation

The *space* (trk or blkgrp) at offset *offset* and length *length* failed validation. *id* is the trk or blkgrp number. Either the space did not uncompress successfully or the uncompressed space contains some kind of error. This error is detected during check level 3 validation.

Action

The space will be recovered.

HHCCU700E

HHCCU700E open error: *error text*

Explanation

Open failed for the file. The text associated with the error number is displayed.

Action

Processing for the file terminates.

HHCCU701E

HHCCU701E fstat error: *error text*

Explanation

The file status system call failed. The text associated with the error number is displayed.

Action

Function processing terminates. Probable Hercules logic error. Contact the Hercules mailing list for assistance.

HHCCU702E

HHCCU702E lseek error offset *offset*: error text

Explanation

File reposition to offset *offset* failed. The text associated with the error number is displayed.

Action

Function processing terminates. Probable Hercules logic error. Contact the Hercules mailing list for assistance.

HHCCU703E

HHCCU703E read error rc=*retcode* offset *offset* len *length*: error text

Explanation

A read failed at offset *offset* for length *length*. If *retcode* is not negative then the read was incomplete and the value indicates how many bytes were read. Otherwise the text associated with the error number is displayed.

Action

Function processing terminates. Possible Hercules logic error. Possible hardware error. Contact the hercules mailing list for assistance.

HHCCU704E

HHCCU704E write error rc=*retcode* offset *offset* len *length*: error text

Explanation

A write failed at offset *offset* for length *length*. If *retcode* is not negative then the write was incomplete and the value indicates how many bytes were written. Otherwise the text associated with the error number is displayed.

Action

Function processing terminates. Possible Hercules logic error. Possible hardware error. Contact the hercules mailing list for assistance.

HHCCU705E

HHCCU705E malloc error, size *size*: error text

Explanation

Malloc (allocate memory) failed for size *size*.

Action

Function processing terminates. Try reducing Hercules storage requirements (e.g. mainsize).

HHCCU706E

HHCCU706E calloc error, size *size*: *error text*

Explanation

Calloc (allocate cleared memory) failed for size *size*.

Action

Function processing terminates. Try reducing Hercules storage requirements (eg mainsize).

HHCCU707E

HHCCU707E OPENED bit is on, use -f

Explanation

The file OPENED bit is on in the cckd header but *-f* was not specified.

Action

File processing terminates. Make sure the file is not in use. If it is not, try the command again specifying the *-f* option.

HHCCU708E

HHCCU708E chkdsk errors

Explanation

The utility called cckd_chkdsk for the file and it returned in error.

Action

File processing terminates. Perform the actions suggested by the preceding cckd_chkdsk errors.

HHCCU900E

HHCCU900E dasd lookup error *type=type* *cy/s=cy/s*

Explanation

The device type *type* from the device header along with the number of cylinders *cy/s* did not match a table entry in dasdtab.c. Note that *type* is the last two bytes of the device type (eg 90 for a 3390 device type).

Action

Function processing terminates. Specify the correct file name or manually correct the device header.

HHCCU901E

HHCCU901E bad trksize: *size1*, expecting *size2*

Explanation

The track size *size1* from the device header does not match the track size *size2* from the table entry in dasdtab.c.

Action

Function processing terminates. Specify the correct file name or manually correct the device header.

HHCCU902E

HHCCU902E bad number of heads: *heads1*, expecting *heads2*

Explanation

The number of heads *heads1* from the device header does not match the number of heads *heads2* from the table entry in `dasdtab.c`.

Action

Function processing terminates. Specify the correct file name or manually correct the device header.

HHCCU903E

HHCCU903E bad `numl1tab': *nbr1*, expecting *nbr2*

Explanation

The number of L1 table entries *nbr1* in the cckd device header does not match the number calculated *nbr2*. The number calculated is the number of cylinders times the number of heads (i.e. the number of tracks) divided by 256, rounded up by 1 if there is a remainder.

Action

Function processing terminates. Specify the correct file name or manually correct the device headers.

HHCCU904E

HHCCU904E file too small to contain L1 table: *%size1*, need *size2*

Explanation

The size of the file *size1* is not large enough to contain all L1 table entries; the size required is *size2*. The minimum size of a cckd file is $512 + 512 + (4 * \text{number of L1 entries})$.

Action

Function processing terminates. Specify the correct file name.

HHCCU905E

HHCCU905E not enough file space for recovery

Explanation

During phase 2 recovery there was not enough space in the maximum file size to contain the rebuilt L2 tables. This is an unusual situation and probably indicates some kind of programming error.

Action

Function processing terminates. The file has not been updated. Contact the hercules mailing list for assistance.

HHCCU910E

HHCCU910E error during swap

Explanation

Error occurred during `cckd_swap()`.

Action

See the preceding error messages.

HHCCU999E

HHCCU999E not a compressed file

Explanation

The first 8 bytes of the file did not match an expected identifier. For a `cckd` file, the identifier must be either `CKD_C370` or `CKD_S370`. For a `cfba` file, the identifier must be either `FBA_C370` or `FBA_S370`.

Action

Function processing terminates. Specify the correct file name.

10. Messages HHCDAnnns - DASD Emulation (CKD, CCKD and FBA)

HHCDAnnns

Messages HHCDAnnns are not yet documented.

11. Messages HHCDCnnns - DASDCOPY Utility

HHCDC001E

HHCDC001E *programe: filename open error: error*

Explanation

An error was encountered when trying to open the input file named *filename* to determine its type. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDC002E

HHCDC002E *programe: filename read error: error*

Explanation

An error was encountered when trying to read the input file named *filename* to determine its type. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDC003E

HHCDC003E *programe: filename open failed*

Explanation

An error was encountered when trying to open the input file named *filename* for copying. A previous message described the error.

Action

Correct the error and retry the operation.

HHCDC004E

HHCDC004E *programe: ckd lookup failed for size cyls*

Explanation

There was no disk drive table entry that matched the number of cylinders in the CKD source file, *size*. The program cannot determine how much data to copy.

Action

Correct the error and retry the operation.

HHCDC005E

HHCDC005E *progrname: fba lookup failed, blks size*

Explanation

There was no disk drive table entry that matched the number of blocks in the FBA source file, *size*. The program cannot determine how much data to copy.

Action

Correct the error and retry the operation.

HHCDC006E

HHCDC006E *progrname: filename create failed*

Explanation

An error was encountered when trying to create the output file named *filename*. A previous message described the error.

Action

Correct the error and retry the operation.

HHCDC007E

HHCDC007E *progrname: filename open failed*

Explanation

An error was encountered when trying to open the newly created output file named *filename*. A previous message described the error.

Action

Correct the error and retry the operation.

HHCDC008E

HHCDC008E *progrname: filename read error (track|block) number stat=status*

Explanation

An error was encountered when trying to read a block or track from the input file named *filename*. The block or track is number *number*. The status returned is shown as *status*.

Action

Correct the error and retry the operation.

HHCDC009E

HHCDC009E *programe: filename write error (track|block) number stat=status*

Explanation

An error was encountered when trying to read a block or track from the input file named *filename*. The block or track is number *number*. The status returned is shown as *status*.

Action

Correct the error and retry the operation.

HHCDC010I

HHCDC010I *Copy successful !!!*

Explanation

The copy operation has completed successfully.

Action

None.

12. Messages HHCDGnnns - Dyngui.DLL

HHCDG001I

HHCDG001I dyngui.dll - *name* - version *vers* initiated

Explanation

The dyngui loadable module was successfully loaded and initiated.

Action

None. This message is informational only.

HHCDG002I

HHCDG002I dyngui.dll terminated

Explanation

The dyngui loadable module was successfully terminated.

Action

None. This message is informational only.

HHCDG003S

HHCDG003S select failed on input stream: *errmsg*

Explanation

The socket select function call failed on the input stream. *errmsg* describes the exact error.

Action

None; this is a fatal error, the system is immediately terminated.

HHCDG004S

HHCDG004S read failed on input stream: *errmsg*

Explanation

An unrecoverable i/o error occurred while reading from the input stream. *errmsg* describes the exact error.

Action

None; this is a fatal error; the system is immediately terminated.

HHCDG005E

HHCDG005E Device query buffer overflow! (device=*xxxx*)

Explanation

The device query buffer is not large enough to hold all of the information returned by the device handler. *xxxx* is the device whose information was being queried at the time the error occurred.

Action

The system attempts to continue functioning but unpredictable results may occur (i.e. the system could crash). You should report this error to the Hercules developers immediately so that they can build you a new dyngui.dll with a larger device query buffer. Since the dyngui.dll is an unloadable module you will need to restart Hercules in order to begin using the newly fixed version of dyngui.dll.

HHCDG006S

HHCDG006S malloc pszInputBuff failed: *errmsg*

Explanation

There was not enough virtual memory on the host system to satisfy the malloc request for the input stream buffer. *errmsg* describes the exact error.

Action

None; this is a fatal error, the system is immediately terminated. You should increase the size of your host system's virtual memory allocation so that there is enough for Hercules to run, or else decrease the amount of memory that Hercules needs in order to run (e.g. decrease your MAINSIZE value).

HHCDG007S

HHCDG007S malloc pszCommandBuff failed: *errmsg*

Explanation

There was not enough virtual memory on the host system to satisfy the malloc request for the command processing buffer. *errmsg* describes the exact error.

Action

None; this is a fatal error, the system is immediately terminated. You should increase the size of your host system's virtual memory allocation so that there is enough for Hercules to run, or else decrease the amount of memory that Hercules needs in order to run (e.g. decrease your MAINSIZE value).

13. Messages HHCDInnns - DASDINIT Utility

HHCDI001I

HHCDI001I DASD initialization successfully completed.

Explanation

The requested DASD volume has been successfully initialized and is ready for use.

Action

None.

HHCDI002I

HHCDI002I DASD initialization unsuccessful.

Explanation

Initialization of the requested DASD volume was not successful.

Action

Refer to preceding error messages to determine the cause.

14. Messages HHCDLnnns - DASDLOAD Utility

HHCDL001E

HHCDL001E Cannot open *filename*: *error*

Explanation

The control file named *filename* cannot be opened. The error is described by *error*.

Action

Correct the error and rerun dasdload.

HHCDL002E

HHCDL002E Volume serial statement missing from *filename*

Explanation

The control file named *filename* does not contain a volume serial statement. A volume serial is required.

Action

Supply a volume serial statement and rerun dasdload.

HHCDL003E

HHCDL003E Volume serial *serial* in *filename* line *lineno* is not valid

Explanation

The volume serial *serial* supplied in line *lineno* of the control file named *filename* is not valid. It must be from one to six characters long.

Action

Supply a valid volume serial and rerun dasdload.

HHCDL004E

HHCDL004E Device type *type* in *filename* line *lineno* is not recognized

Explanation

The device type *type* specified in line *lineno* of the control file named *filename* is not a supported CKD device.

Action

Specify a supported CKD device type and rerun dasdload.

HHCDL005E

HHCDL005E *count* in *filename* line *lineno* is not a valid cylinder count

Explanation

The requested number *count* of cylinders for the volume in line *lineno* of the control file named *filename* is invalid. It must be a decimal number.

Action

Supply a valid cylinder count and rerun dasdload.

HHCDL006I

HHCDL006I Creating *type* volume *serial*: *tracks* trks/cyl, *length* bytes/track

Explanation

The volume named *serial* of type *type* is being created with *tracks* tracks per cylinder and *length* bytes per track.

Message Level

0.

Action

None.

HHCDL007E

HHCDL007E Cannot create *filename*

Explanation

The DASD image file named *filename* cannot be created. A previous message described the problem.

Action

Correct the reported error and rerun dasdload.

HHCDL008E

HHCDL008E Cannot open *filename*

Explanation

The DASD image file named *filename* could not be opened. A previous message described the problem.

Action

Correct the reported error and rerun dasdload.

HHCDL009I

HHCDL009I Loading *type* volume *serial*

Explanation

The newly created volume with serial *serial* of type *type* is being loaded.

Message Level

0.

Action

None.

HHCDL010E

HHCDL010E Cannot obtain storage for DSCB pointer array: *error*

Explanation

An attempt to obtain storage for the array of DSCB pointers, which will populate the VTOC, failed. The error is described by *error*.

Action

Correct the error and rerun dasdload.

HHCDL011E

HHCDL011E Invalid statement in *filename* line *lineno*

Explanation

An invalid control statement was found at line *lineno* of the control file named *filename*.

Action

Correct the invalid statement and rerun dasdload.

HHCDL012I

HHCDL012I Creating dataset *dsn* at cyl *cylinder* head *head*

Explanation

The dataset named *dsn* is being created. It begins at cylinder *cylinder* head *head*.

Message level

1

Action

None.

HHCDL013I

HHCDL013I Dataset *dsn* contains *size* tracks

Explanation

The dataset named *dsn* is *size* tracks long.

Message level

2

Action

None.

HHCDL014I

HHCDL014I Free space starts at cyl *cylinder* head *head*

Explanation

Free space on the volume begins at cylinder *cylinder* head *head* and extends to the end of the volume.

Message level

1

Action

None.

HHCDL015W

HHCDL015W Volume exceeds *cylinders*

Explanation

The amount of space used on the volume exceeds the number of cylinders *cylinders* requested in the control file. The number of cylinders was explicitly requested instead of being allowed to default to the size of a full volume for the device type. The volume has been extended to accomodate the data written.

Action

Specify more cylinders in the control file or allow the number to default.

HHCDL016I

HHCDL016I Total of *count* cylinders written to *filename*

Explanation

A total of *count* cylinders have been written to the DASD image file named *filename*.

Message level

0

Action

None.

HHCDL017I

HHCDL017I Updating VTOC pointer *pointer*

Explanation

The pointer to the VTOC in the volume label is being updated to point to the VTOC at location *pointer*.

Message level

5

Action

None.

HHCDL018E

HHCDL018E Cannot read VOL1 record

Explanation

An attempt to read the volume label failed. A previous message described the error.

Action

Correct the error and rerun dasdload.

HHCDL019E

HHCDL019E Cannot read *filename* line *lineno*: *error*

Explanation

An error was encountered while trying to read the statement at line number *lineno* of the control file named *filename*. The error is described by *error*.

Action

Correct the error and rerun dasdload.

HHCDL020E

HHCDL020E Line too long in *filename* line *lineno*

Explanation

The line at line number *lineno* of the control file named *filename* is too long to be processed. This error can be caused by failing to terminate the last line with an end-of-line marker.

Action

Correct the error and rerun dasdload.

HHCDL021E

HHCDL021E DSNNAME or initialization method missing

Explanation

Either the dataset name or the method to be used to initialize it is missing from the control file. Both are required.

Action

Supply the missing value and rerun dasdload.

HHCDL022E

HHCDL022E Invalid initialization method: *method*

Explanation

The method specified to initialize the dataset *method* is invalid. It must be one of xmit, vs, empty, dip, cvol, vtoc, or seq.

Action

Correct the initialization method and rerun dasdload.

HHCDL023E

HHCDL023E Initialization file name missing

Explanation

A dataset was specified as being initialized by either the xmit, vs, or seq initialization methods but no source file was specified to provide the data to be loaded.

Action

Specify a source file name or specify the empty dataset initialization method if the dataset is not to be loaded.

HHCDL024E

HHCDL024E Invalid allocation units: *units*

Explanation

The allocation unit specified *units* is invalid. It must be either cyl or trk.

Action

Specify a valid allocation unit and rerun dasdload.

HHCDL025E

HHCDL025E Invalid primary space: *space*

Explanation

The primary space requested *space* is not a valid decimal number greater than 0.

Action

Specify a valid space request and rerun dasdload.

HHCDL026E

HHCDL026E Invalid secondary space: *space*

Explanation

The secondary space requested *space* is not a valid decimal number greater than 0.

Action

Specify a valid space request and rerun dasdload.

HHCDL027E

HHCDL027E Invalid directory space: *space*

Explanation

The PDS directory space requested *space* is not a valid decimal number greater than 0.

Action

Specify a valid space request and rerun dasdload.

HHCDL028E

HHCDL028E Invalid dataset organization: *dsorg*

Explanation

The requested dataset organization *dsorg* is invalid. It must be one of is, ps, da, or po.

Action

Specify a valid dataset organization and rerun dasdload.

HHCDL029E

HHCDL029E Invalid record format: *recfm*

Explanation

The requested record format *recfm* is invalid. It must be one of f, fb, fbs, v, vb, vbs, or u.

Action

Specify a valid record format and rerun dasdload.

HHCDL030E

HHCDL030E Invalid logical record length: *lrecl*

Explanation

The requested logical record length *lrecl* is invalid. It must be a decimal number between 0 and 32767.

Action

Specify a valid logical record length and rerun dasdload.

HHCDL031E

HHCDL031E Invalid block size: *blksize*

Explanation

The requested block size *blksize* is invalid. It must be a decimal number between 0 and 32767.

Action

Specify a valid block size and rerun dasdload.

HHCDL032E

HHCDL032E Invalid key length: *keylen*

Explanation

The requested key length *keylen* is invalid. It must be a decimal number between 0 and 255.

Action

Specify a valid key length and rerun dasdload.

HHCDL033E

HHCDL033E CCHH=*cchh* not found in extent table

Explanation

The absolute track address *cchh* was not found in the table listing the locations occupied by the dataset being loaded. There is likely a problem with the input file.

Action

Correct the input file and rerun dasdload.

HHCDL034E

HHCDL034E Cannot open *filename*: *error*

Explanation

The file named *filename*, which was specified as the source of IPL text to be written to the volume, could not be opened. The error is described by *error*.

Action

Correct the error and rerun dasdload.

HHCDL035E**HHCDL035E Cannot read *filename*: error****Explanation**

An error was encountered while reading the IPL text file named *filename*. The error is described by *error*. If no error is reported, the file did not contain an integral number of 80-byte card images.

Action

Correct the reported error or supply a valid IPL text file consisting of 80-byte card images and rerun dasdload.

HHCDL036E**HHCDL036E *filename* is not a valid object file****Explanation**

The IPL text file named *filename* is not a valid object file. A record read from the file did not contain the required flag in the first byte.

Action

Supply a valid object file and rerun dasdload.

HHCDL037I**HHCDL037I IPL text address=*addr* length=*length*****Explanation**

The object code from the current record of the IPL text file will be loaded into memory at address *address*, and is *length* bytes long.

Message level

5

Action

None.

HHCDL038E**HHCDL038E TXT record in *filename* has invalid count *length*****Explanation**

A text record in the IPL text file named *filename* has an invalid length *length*. The length cannot exceed 56.

Action

Supply a valid IPL text file and rerun dasdload.

HHCDL039E

HHCDL039E IPL text in *filename* exceeds *buflen* bytes

Explanation

The IPL text file named *filename* is too long to fit in the available space on the volume. The IPL text cannot exceed *buflen* bytes in length.

Action

Supply a shorter IPL text file or specify a volume with a larger track size and rerun dasdload.

HHCDL040E

HHCDL040E Input record CCHHR=*cchhr* exceeds output device track size

Explanation

The block to be written at absolute address *cchhr* is too large to fit on a track on the disk being loaded.

Action

Specify a device with a larger track size and rerun dasdload.

HHCDL041E

HHCDL041E Dataset exceeds extent size: *reltrk=track*, *maxtrk=maxtrk*

Explanation

The data to be written to the dataset is too large for the space requested for it. If the space request was allowed to default, the input file is corrupt.

Action

If the space request was made explicitly, then request more space. If the request was defaulted, supply a valid input file. Rerun dasdload.

HHCDL042E

HHCDL042E Input record CCHHR=*cchhr* exceeds virtual device track size

Explanation

The block to be written at absolute address *cchhr* is too large to fit on a track on the disk being loaded. In addition, this message being issued instead of message HHCDL040E indicates an internal inconsistency in the way Hercules computes the space available on a track.

Action

Specify a device with a larger track size and rerun dasdload. Report the inconsistency to the Hercules development team.

HHCDL043E

HHCDL043E *filename cyl cylinder head head read error*

Explanation

The data at cylinder *cylinder*, head *head* of the disk image file named *filename* could not be read in order to be updated. A previous message described the error.

Action

Correct the previously reported error and rerun dasdload.

HHCDL044E

HHCDL044E *filename cyl cylinder head head invalid track header header*

Explanation

The track header *header* at cylinder *cylinder*, head *head* in the disk image file named *filename* contained an address that did not match the actual address.

Action

Rerun dasdload. If the error persists, report it to the Hercules development team.

HHCDL045E

HHCDL045E *filename cyl cylinder head head record record record not found*

Explanation

The record requested for update at cylinder *cylinder*, head *head*, record *record* of the DASD image file named *filename* was not found.

Action

Rerun dasdload. If the error persists, report it to the Hercules development team.

HHCDL046E

HHCDL046E *Cannot update cyl cylinder head head rec record: Unmatched KL/DL*

Explanation

The record to be written at cylinder *cylinder*, head *head*, record *record* does not have the same key or data length as the record that already exists at that location. This is not allowed for a record update operation.

Action

Rerun dasdload. If the error persists, report it to the Hercules development team.

HHCDL047E

HHCDL047E *filename* cyl *cylinder* head *head* read error

Explanation

A read error was encountered when reading the track at cylinder *cylinder*, head *head*, in the disk image file named *filename*. A previous message described the error.

Action

Correct the error reported by the previous message and rereun dasdload.

HHCDL048I

HHCDL048I Updating cyl *cylinder* head *head* rec *record* kl *keylen* dl *datalen*

Explanation

The record at cylinder *cylinder*, head *head*, record *record* is being updated. It has a key length of *keylen* and data length *datalen*.

Message level

4

Action

None.

HHCDL049E

HHCDL049E Cannot obtain storage for DSCB: *error*

Explanation

An attempt to obtain storage to build a DSCB to describe a dataset on the volume being loaded failed. The error is described by *error*.

Action

Correct the error and rerun dasdload.

HHCDL050E

HHCDL050E DSCB count exceeds *maximum*, increase MAXDSCB

Explanation

There are too many datasets on the volume being loaded and an internal structure in dasdload is full.

Action

Increase the value of the symbol MAXDSCB in the source program and recompile dasdload, then rerun the program.

HHCDL051E

HHCDL051E Cannot obtain storage for DSCB: *error*

Explanation

An attempt to obtain storage to build a DSCB to describe the VTOC on the volume being loaded failed. The error is described by *error*.

Action

Correct the error and rerun dasdload.

HHCDL052E

HHCDL052E DSCB count exceeds *maximum*, increase MAXDSCB

Explanation

There are too many datasets on the volume being loaded and an internal structure in dasdload is full.

Action

Increase the value of the symbol MAXDSCB in the source program and recompile dasdload, then rerun the program.

HHCDL053E

HHCDL053E Cannot obtain storage for DSCB: *error*

Explanation

An attempt to obtain storage to build a DSCB to describe the free space on the volume being loaded failed. The error is described by *error*.

Action

Correct the error and rerun dasdload.

HHCDL054E

HHCDL054E DSCB count exceeds *maximum*, increase MAXDSCB

Explanation

There are too many datasets on the volume being loaded and an internal structure in dasdload is full.

Action

Increase the value of the symbol MAXDSCB in the source program and recompile dasdload, then rerun the program.

HHCDL055E

HHCDL055E VTOC too small, *tracks* tracks required

Explanation

The VTOC allocation of *tracks* is too small to hold the VTOC.

Action

Specify at least *tracks* tracks for the VTOC and rerun dasdload.

HHCDL056E

HHCDL056E Error reading VTOC cyl *cylinder* head *head*

Explanation

The first track of the VTOC could not be read so it could be updated. A previous message described the error.

Action

Correct the error reported by the previous message and rerun dasdload.

HHCDL057I

HHCDL057I VTOC starts at cyl *cylinder* head *head* and is *tracks* tracks

Explanation

The VTOC on the volume being loaded starts at cylinder *cylinder*, head *head* and is *tracks* tracks long.

Message level

1

Action

None.

HHCDL058I

HHCDL058I Format *format* DSCB CCHHR=*cchhr* (TTR=*ttr*) *dsname*

Explanation

The format *format* DSCB is located at absolute address *cchhr* and relative address within the VTOC *ttr*. If *format* is 1, the dataset described by the DSCB is named *dsname*.

Message level

4

Action

None.

HHCDL059I

HHCDL059I Format 0 DSCB CCHHR *cchhr* (TTR=*ttr*)

Explanation

A format 0 (empty) DSCB is located at absolute address *cchhr* and relative address within the VTOC *ttr*.

Message level

4

Action

None.

HHCDL060E

HHCDL060E Error reading track *cyl* *cylinder* head *head*

Explanation

An error was encountered reading the track at cylinder *cyl*, head *head*. A previous message described the error.

Action

Correct the error reported by the previous message and rerun dasdload.

HHCDL061E

HHCDL061E Incomplete text unit

Explanation

An text unit read from the input file was too short to contain a valid header. The input data is probably corrupt.

Action

Supply a valid input file and rerun dasdload.

HHCDL062I

HHCDL062I *position* *tuname* *key* *fields*

Explanation

The text unit at *position* of the input buffer has the name *tuname* and the numeric key value *key*. There are *fields* fields in the text unit.

Message level

4

Action

None.

HHCDL063E

HHCDL063E Too many fields in text unit

Explanation

A text unit was read from the input file that had too many fields in the header for that type of text unit. The input file is probably corrupt.

Action

Supply a valid input file and rerun dasdload.

HHCDL064E

HHCDL064E Incomplete text unit

Explanation

A text unit read from the input file was too short to contain a valid field length. The input data is probably corrupt.

Action

Supply a valid input file and rerun dasdload.

HHCDL065E

HHCDL065E Incomplete text unit

Explanation

A text unit read from the input file was shorter than the length in the field header. The input data is probably corrupt.

Action

Supply a valid input file and rerun dasdload.

HHCDL066E

HHCDL066E *filename* read error: *error*

Explanation

An error was encountered when reading the input file named *filename*. The error is described by *error*.

Action

Correct the error and rerun dasdload.

HHCDL067E

HHCDL067E *filename* invalid segment header: *header*

Explanation

A segment read from the file named *filename* has an invalid header *header*. The input file is probably corrupt.

Action

Supply a valid input file and rerun dasdload.

HHCDL068E**HHCDL068E *filename* first segment indicator expected****Explanation**

A segment read from the file named *filename* should have the first segment indicator set but does not. The input file is probably corrupt.

Action

Supply a valid input file and rerun dasdload.

HHCDL069E**HHCDL069E *filename* first segment indicator not expected****Explanation**

A segment read from the file named *filename* should not have the first segment indicator set but does. The input file is probably corrupt.

Action

Supply a valid input file and rerun dasdload.

HHCDL070E**HHCDL070E *filename* control record indicator mismatch****Explanation**

There was a mismatch between the first segment and the control record. The input file is probably corrupt.

Action

Supply a valid input file and rerun dasdload.

HHCDL071E**HHCDL071E *filename* read error: *error*****Explanation**

An error was encountered when reading a segment from the input file named *filename*. The error is described by *error*.

Action

Correct the error and rerun dasdload.

HHCDL072E

HHCDL072E *filename* read error: *error*

Explanation

An error was encountered when reading a COPYR1 record from the input file named *filename*. The error is described by *error*.

Action

Correct the error and rerun dasdload.

HHCDL073E

HHCDL073E *filename* read error: *error*

Explanation

An error was encountered when reading a COPYR2 record from the input file named *filename*. The error is described by *error*.

Action

Correct the error and rerun dasdload.

HHCDL074E

HHCDL074E *filename* read error: *error*

Explanation

An error was encountered when reading a data block header from the input file named *filename*. The error is described by *error*.

Action

Correct the error and rerun dasdload.

HHCDL075E

HHCDL075E *filename* read error: *error*

Explanation

An error was encountered when reading a data block from the input file named *filename*. The error is described by *error*.

Action

Correct the error and rerun dasdload.

HHCDL076I

HHCDL076I File number: *number*

Explanation

The file being processed is number *number*.

Message level

4

Action

None.

HHCDL077E

HHCDL077E Invalid text unit at offset *offset*

Explanation

An invalid text unit was read from position *offset*. A previous message described the error. The input file is probably corrupt.

Action

Supply a valid input file and rerun dasdload.

HHCDL078I

HHCDL078I File *filenum*: DSNAME=*dsname*

Explanation

The dataset name of file number *filenum* is *dsname*.

Message level

2

Action

None.

HHCDL079I

HHCDL079I DSORG=*dsorg* RECFM=*recfm* LRECL=*lrecl* BLKSIZE=*blksize* KEYLEN=*keylen*
DIRBLKS=*dirblks*

Explanation

For the dataset listed in the preceding HHCDL078I message the dataset organization is *dsorg*, the record format is *recfm*, the logical record length is *lrecl*, the block size is *blksize*, the key length is *keylen* and the directory block count is *dirblks*.

Message level

2

Action
None.

HHCDL080E

HHCDL080E Invalid text unit at offset *offset*

Explanation

An invalid text unit was read from position *offset*. A previous message described the error. The input file is probably corrupt.

Action

Supply a valid input file and rerun dasdload.

HHCDL081E

HHCDL081E COPYR1 record length is invalid

Explanation

The length of the COPYR1 record is invalid. The input file is probably corrupt.

Action

Supply a valid input file and rerun dasdload.

HHCDL082E

HHCDL082E COPYR1 header identifier not correct

Explanation

The header identifier of the COPYR1 record is invalid. The input file is probably corrupt.

Action

Supply a valid input file and rerun dasdload.

HHCDL083E

HHCDL083E COPYR1 unload format is unsupported

Explanation

The COPYR1 record indicates that the file was unloaded in a format that is not supported by dasdload. The file may be corrupt or it may simply be in a newer format than is supported by this version of dasdload.

Action

Supply a supported input file and rerun dasdload.

HHCDL084I

HHCDL084I Original dataset: DSORG=*dsorg* RECFM=*rcfm* LRECL=*lrecl* BLKSIZE=*blksize* KEYLEN=*keylen*

Explanation

For the original dataset, the dataset organization is *dsorg*, the record format is *rcfm*, the logical record length is *lrecl*, the block size is *blksize*, the key length is *keylen* and the directory block count is *dirblks*.

Message level

2

Action

None.

HHCDL085I

HHCDL085I Dataset was unloaded from device type *ucbtype* (*device*)

Explanation

The dataset was unloaded from a *device* device, with UCB device type *ucbtype*.

Message level

2

Action

None.

HHCDL086I

HHCDL086I Original device has *cylinders* *cyls* and *heads* *heads*

Explanation

The device listed in the preceding HHCDL085I message has *cylinders* cylinders and *heads* heads.

Message level

2

Action

None.

HHCDL087E

HHCDL087E COPYR2 record length is invalid

Explanation

The length of the COPYR2 record just read is not valid. The input file is probably corrupt.

Action

Supply a valid input file and rerun dasdload.

HHCDL088E

HHCDL088E Invalid number of extents *extents*

Explanation

The number of extents reported in the COPYR2 record is invalid, either less than 1 or more than 16. The input file is probably corrupt.

Action

Supply a valid input file and rerun dasdload.

HHCDL089I

HHCDL089I Extent *extent*: Begin CCHH=*begcchh* End CCHH=*endcchh* Tracks=*tracks*

Explanation

For extent number *extent*, the extent starts at cylinder and head *begcchh*, and ends at *endcchh*, for a total of *tracks* tracks.

Message level

4

Action

None.

HHCDL090I

HHCDL090I End of directory

Explanation

The end of the PDS directory has been reached.

Message level

3

Action

None.

HHCDL091E

HHCDL091E Directory block record length is invalid

Explanation

The directory block read from the input file has the wrong length. It must be 276 bytes long. The input file is probably corrupt.

Action

Supply a valid input file and rerun dasdload.

HHCDL092E

HHCDL092E Cannot obtain storage for directory block: error

Explanation

An attempt to obtain storage for the directory block being processed failed. The error is described by *error*.

Action

Correct the error and rerun dasdload.

HHCDL093E

HHCDL093E Number of directory blocks exceeds *maxdblk*, increase MAXDBLK

Explanation

The number of directory blocks in the dataset being processed exceeds the size of an internal control structure. The maximum number is *maxdblk*.

Action

Increase the value of the constant MAXDBLK in the program source and recompile dasdload.

HHCDL094E

HHCDL094E Directory block byte count is invalid

Explanation

The length of the current directory block is invalid. The input file is probably corrupt.

Action

Supply a valid input file and rerun dasdload.

HHCDL095I

**HHCDL095I (Alias|Member) *memname* TTR=*ttr*
Userdata=*userdata***

Explanation

The alias or member named *memname* is located at relative address *ttr*. If user data is present, it is printed as *userdata*.

Message level

3

Action

None.

HHCDL096I

HHCDL096I Member *name* TTR=*oldttr* replaced by *newttr*

Explanation

In the directory entry for member *name*, the old pointer to the member *oldttr* was replaced by the member's actual relative address *newttr*.

Message level

4

Action

None.

HHCDL097E

HHCDL097E Member *name* TTR=*ttr* not found in dataset

Explanation

A request was made to update the directory entry for the member named *name* but there was no directory entry to update.

Action

This is likely an internal logic error. Report the error to the Hercules development team.

HHCDL098I

HHCDL098I Updating note list for member *name* at TTR=*ttr* CCHHR=*cchhr*

Explanation

The note list for the member named *name*, at relative address *ttr*, absolute address *cchhr*, is being updated.

Message level

4

Action

None.

HHCDL099E

HHCDL099E *filename* cyl *cylinder* head *head* read error

Explanation

An attempt to read the track in the DASD image file named *filename* at cylinder *cylinder*, head *head*, failed. A previous error described the failure.

Action

Correct the error reported by the previous message and rerun dasdload.

HHCDL100E

HHCDL100E *filename cyl cylinder head head invalid track header header*

Explanation

The header *header* of the track in the DASD image file named *filename* at cylinder *cylinder*, head *head* did not agree with the actual address of the track. This is probably an internal logic error.

Action

Report the error to the Hercules development team.

HHCDL101E

HHCDL101E *filename cyl cylinder head head rec record note list record not found*

Explanation

A request was made to update a note list record at cylinder *cylinder*, head *head*, record *record*, but the record was not found. The input dataset may be corrupt.

Action

Supply a valid input dataset and rerun dasdload.

HHCDL102E

HHCDL102E Member *member* note list at cyl *cylinder* head *head* rec *record* dlen *datalen* is too short for *numttrs* TTRs

Explanation

The data length *datalen* of the note list record for member *member* at cylinder *cylinder*, head *head*, record *record*, is too short to contain the requested number *numttrs* of record pointers. The input dataset is probably corrupt.

Action

Supply a valid input dataset and rerun dasdload.

HHCDL103E

HHCDL103E *filename track read error cyl cylinder head head*

Explanation

An attempt to read the track in the DASD image file named *filename* at cylinder *cylinder*, head *head*, failed. A previous error described the failure.

Action

Correct the error reported by the previous message and rerun dasdload.

HHCDL104I

HHCDL104I Updating cyl *cylinder* head *head* rec *record* kl *keylen* dl *datalen*

Explanation

The record at cylinder *cylinder*, head *head*, record *record*, with key length *keylen* and data length *datalen* is being updated.

Message level

4

Action

None.

HHCDL105E

HHCDL105E Directory block byte count is invalid

Explanation

The length of the current directory block is invalid. The input file is probably corrupt.

Action

Supply a valid input file and rerun dasdload.

HHCDL106E

HHCDL106E Cannot open file *filename*: *error*

Explanation

An attempt to open the IEBCOPY input file named *filename* failed. The error is described by *error*.

Action

Correct the error and rerun dasdload.

HHCDL107E

HHCDL107E Cannot obtain input buffer: *error*

Explanation

An attempt to obtain a 64K byte input buffer for reading the IEBCOPY input file failed. The error is described by *error*.

Action

Correct the error and rerun dasdload.

HHCDL108E

HHCDL108E Cannot obtain storage for directory block array:*error*

Explanation

An attempt to obtain storage for the internal array used to store directory blocks failed. The error is described by *error*.

Action

Correct the error and rerun *dasdload*.

HHCDL109E

HHCDL109E Cannot obtain storage for TTR table: *error*

Explanation

An attempt to obtain storage for the internal array used to store track pointers for later conversion failed. The error is described by *error*.

Action

Correct the error and rerun *dasdload*.

HHCDL110I

HHCDL110I Processing file *filename*

Explanation

The input file named *filename* is being processed.

Message level

1

Action

None.

HHCDL111I

HHCDL111I Control record: *rename* length *length*

Explanation

A control record named *rename* of length *length* has been read.

Message level

4

Action

None.

HHCDL112I

HHCDL112I File number: *filenum* ((not) selected)

Explanation

The data file, number *filenum*, was (or was not) selected for processing.

Message level

4

Action

None.

HHCDL113I

HHCDL113I Data record: length *length*

Explanation

A data record of length *length* has been read.

Message level

4

Action

None.

HHCDL114E

HHCDL114E write error: input record CCHHR=*cchhr* (TTR=*ttr*) KL=*keylen* DL=*datalen*

Explanation

An error was encountered writing the data record at absolute address *cchhr*, relative address *ttr*, with key length *keylen* and data length *datalen*. A previous message described the error.

Action

Correct the error described by the previous message and rerun dasdload.

HHCDL115I

HHCDL115I CCHHR=*incchhr* (TTR=*inttr*) KL=*keylen* DL=*datalen* -> CCHHR=*outcchhr* (TTR=*outttr*)

Explanation

The record at absolute address *incchhr*, relative address *inttr*, with key length *keylen* and data length *datalen*, is being written to the output DASD image at absolute address *outcchhr*, relative address *outttr*.

Message level

4

Action

None.

HHCDL116E

HHCDL116E TTR count exceeds *maxttr*, increase MAXTTR

Explanation

The list of relative address pointers exceeds the size of the internal array used to contain them, *maxttr*.

Action

Increase the constant MAXTTR in the program source and recompile dasdload.

HHCDL117I

HHCDL117I Catalog block at cyl *cylinder* head *head* rec *record*

Explanation

A catalog record has been written to disk at cylinder *cylinder*, head *head* and record *record*.

Message level

4

Action

None.

HHCDL118I

HHCDL118I Catalog block at cyl *cylinder* head *head* rec *record*

Explanation

A catalog index record has been written to disk at cylinder *cylinder*, head *head* and record *record*.

Message level

4

Action

None.

HHCDL119I

HHCDL119I Catalog block at cyl *cylinder* head *head* rec *record*

Explanation

An empty catalog record has been written to disk at cylinder *cylinder*, head *head* and record *record*.

Message level

4

Action

None.

HHCDL120I

HHCDL120I DIP complete at cyl *cylinder* head *head* record *record*

Explanation

The LOGREC dataset has been initialized. The last block written was at cylinder *cylinder*, head *head*, record *record*.

Message level

3

Action

None.

HHCDL121E

HHCDL121E SEQ dsorg must be PS or DA: dsorg=*dsorg*

Explanation

The dataset organization specified for the input dataset was *dsorg*. It must be either PS or DA but is not.

Action

Specify a valid dataset organization for sequential file processing or specify the correct processing option for the file being loaded and rerun dasdload.

HHCDL122E

HHCDL122E SEQ recfm must be F or FB: recfm=*recfm*

Explanation

The record format specified for the input dataset was *recfm*. It must be either F or FB but is not.

Action

Specify a valid record format for sequential file processing and rerun dasdload.

HHCDL123E

HHCDL123E SEQ invalid lrecl or blkisz: lrecl=*lrecl* blkisz=*blkisz*

Explanation

The logical record length specified for the input dataset was *lrecl*, and the block size was *blkisz*. Either the block size was not a multiple of the logical record length and the record format was specified as FB or the block size was different from the logical record length and the record format was specified as F.

Action

Specify a valid logical record length and block size for sequential file processing and rerun dasdload.

HHCDL124E

HHCDL124E SEQ keyIn must be 0 for blocked files

Explanation

The key length was specified as nonzero and the record format was specified as FB. This combination is invalid.

Action

If a key is required, specify a record format of F. If no key is required, specify a key length of 0. Rerun dasdload.

HHCDL125E

HHCDL125E Cannot open *filename*: error

Explanation

An error was encountered when attempting to open the input file named *filename*. The error is described by *error*.

Action

Correct the error and rerun dasdload.

HHCDL126E

HHCDL126E Cannot stat *filename*: error

Explanation

An error was encountered when attempting to obtain the size of the file named *filename*. The error is described by *error*.

Action

Correct the error and rerun dasdload.

HHCDL127E

HHCDL127E *filename* cyl *cylinder* head *head* read error

Explanation

An attempt to read the track in the DASD image file named *filename* at cylinder *cylinder*, head *head*, failed. A previous error described the failure.

Action

Correct the error reported by the previous message and rerun dasdload.

HHCDL128E

HHCDL128E *filename* read error: *error*

Explanation

An error was encountered reading the input file named *filename*. The error is described by *error*.

Action

Correct the error and rerun dasdload.

15. Messages HHCDSnnns - DASDISUP Utility

HHCDS001E

HHCDS001E Cannot obtain storage for member array: *error*

Explanation

An attempt to obtain storage for the array of SYS1.SVCLIB members failed. The error is described by *error*.

Action

Correct the error and rerun dasdisup.

HHCDS002I

HHCDS002I End of directory: *count* members selected

Explanation

The end of the SYS1.SVCLIB directory has been reached. *count* members have been selected for processing.

Action

None.

HHCDS003E

HHCDS003E Directory block byte count is invalid

Explanation

The length of the directory block read is invalid. The SYS1.SVCLIB directory is probably corrupt.

Action

Rebuild SYS1.SVCLIB and rerun dasdisup.

HHCDS004E

HHCDS004E Number of members exceeds MAX_MEMBERS

Explanation

SYS1.SVCLIB has too many members to fit in the array used to store their information.

Action

Increase the value of MAX_MEMBERS in dasdisup.c and recompile the program, then run it again.

HHCDS005E

HHCDS005E Member *member* TTR count is zero

Explanation

The member named *member* has no data associated with it. Since aliases have been skipped already, this means that the SYS1.SVCLIB directory is corrupt.

Action

Rebuild SYS1.SVCLIB and run dasdisup again.

HHCDS006W

HHCDS006W Member *member* is not single text record

Explanation

The member named *member* is not contained in a single text record. This is an invalid condition. The member will be skipped later and message HHCDS011E will be issued.

Action

If this member must be processed, rebuild SYS1.SVCLIB and rerun dasdisup.

HHCDS007W

HHCDS007W Member *member* size *size* exceeds X'7F8' bytes

Explanation

The member named *member* is too long. The maximum length of an OS/360 SVC load module is X'7F8' (2040 decimal) bytes. The member will be processed but OS/360 may not process it correctly.

Action

Correct the member in SYS1.SVCLIB and rerun dasdisup.

HHCDS008W

HHCDS008W Member *member* size *size* is not a multiple of 8

Explanation

The member named *member* is not a multiple of 8 bytes long. Its actual size is *size*. This is not valid for an OS/360 load module. OS/360 will issue an ABEND when an attempt is made to load the module.

Action

Correct the member in SYS1.SVCLIB and rerun dasdisup.

HHCDS009I

HHCDS009I Alias *alias* skipped

Explanation

The alias named *alias* has been skipped, since no processing is necessary for it.

Action

None.

HHCDS010I

HHCDS010I Member *member* skipped

Explanation

The member named *member* has been skipped, since it does not have an XCTL table.

Action

If the member should have an XCTL table, rebuild it in SYS1.SVCLIB and rerun dasdisup.

HHCDS011E

HHCDS011E Member *member* has multiple text records

Explanation

The member named *member* has multiple text records. This is not a valid condition for an OS/360 SVC module. The member will not be processed. Message HHCDS006W was issued for this member earlier.

Action

If this member must be processed, rebuild it in SYS1.SVCLIB and rerun dasdisup.

HHCDS012E

HHCDS012E Member *member* has invalid TTR *ttr*

Explanation

The pointer to the text record for the member named *member* is invalid. The pointer found is *ttr*. The member cannot be located to be processed. The SYS1.SVCLIB directory is probably corrupt.

Action

Rebuild SYS1.SVCLIB and rerun dasdisup.

HHCDS013I

HHCDS013I Processing member *member* text record TTR=*ttr* CCHHR=*cchhr*

Explanation

The member named *member* is being processed. Its relative location is *ttr* and its absolute location is *cchhr*.

Action

None.

HHCDS014E

HHCDS014E Member *member* error reading TTR *ttr*

Explanation

An attempt to read the member named *member*, at the relative location *ttr*, failed. The member cannot be processed.

Action

Rebuild SYS1.SVCLIB and rerun dasdisup. If this is unsuccessful, rebuild the entire DASD volume.

HHCDS015E

HHCDS015E Member *member* TTR *ttr* text record length *length* is not valid

Explanation

The length *length* of the text record at location *ttr* of the member named *member* is less than 8, greater than 1024, or not a multiple of 8. All of these conditions must be met for the length to be valid. The member is probably corrupt.

Action

Rebuild the member in SYS1.SVCLIB and rerun dasdisup.

HHCDS016E

HHCDS016E Member *member* TTR *ttr* text record length *textlength* does not match length *dirlength* in directory

Explanation

The length *textlength* of the text record at location *ttr* is not the same as the length *dirlength* in the directory entry for member *member*. Either the member, or the directory, is probably corrupt.

Action

Rebuild the member in SYS1.SVCLIB and rerun dasdisup. If this does not correct the problem, rebuild SYS1.SVCLIB in its entirety.

HHCDS017E

HHCDS017E Member *member* TTR *ttr* XCTL table improperly terminated

Explanation

The XCTL table in member *member* at location *ttr* runs past the end of the text record. The member is probably corrupt.

Action

Rebuild the member and rerun dasdisup.

HHCDS018I

HHCDS018I *member* (Alias|Member) skipped

Explanation

The member or alias named *member* is not an Open, Close, or EOVS module, and so does not have an XCTL table that needs to be updated. It has been skipped.

Action

None.

HHCDS019I

HHCDS019I In member *member*: *reference* TTRL=*ttrl* *status*

Explanation

A reference to the member named *reference* in the member named *member* was found, the referenced member is at the location *ttrl* in the table. *status* is optional; it may be one of:

** Member *reference* not found

The referenced member was not found in SYS1.SVCLIB. The reference cannot be updated.

replaced by TTRL=*newttrl* *flag*

The reference was updated to point to the referenced member's actual location at *newttrl*. If *flag* is ****, the actual length of the referenced member is different from the length of the member in the reference pointer.

Action

None.

16. Messages HHCDTnnns - DASDCAT Utility

HHCDT001E

HHCDT001E failed to open image *filename*

Explanation

An error was encountered trying to open the DASD image file named *filename*. A previous message described the error.

Action

Correct the error and rerun dasdcat.

HHCDT002E

HHCDT002E Can't make 80 column card images from block length *length*

Explanation

A block read from the member specified is not a multiple of 80 characters long, and so cannot be split evenly into 80-character card images. The actual length read is *length*.

Action

Select a different member, or omit the c flag from the member specification.

HHCDT003E

HHCDT003E Directory block byte count is invalid

Explanation

The length of a PDS directory block in the specified dataset is invalid. The PDS directory is corrupt or the dataset is not a PDS.

Action

Make sure the dataset specified is a PDS (partitioned dataset). If it is, then the dataset is corrupt.

HHCDT004E

HHCDT004E non-PDS-members not yet supported

Explanation

This version of dasdcat does not support reading sequential datasets.

Action

Specify a PDS as input to dasdcat.

HHCDT005E

HHCDT005E unknown dataset name option: '*option*'

Explanation

An invalid option was specified on the dataset name specification. Only the options 'a' and 'c' are valid.

Action

Remove the invalid option from the dataset name specification and rerun dasdcat.

17. Messages HHCDU001I - DASD Utilities Common Functions

HHCDU001I

HHCDU001I Updating cyl *cylinder* head *head*

Explanation

The track at cylinder number *cylinder* and head number *head* is being rewritten after being modified. This message is only issued if verbose message reporting has been selected.

Action

None.

HHCDU002E

HHCDU002E *filename* write track error: stat=*status*

Explanation

An attempt to rewrite a track from the DASD image named *filename* failed. The status returned was *status*.

Action

Correct the error and retry the operation.

HHCDU003I

HHCDU003I Reading cyl *cylinder* head *head*

Explanation

The track at cylinder number *cylinder* and head number *head* is being read. This message is only issued if verbose message reporting has been selected.

Action

None.

HHCDU004E

HHCDU004E *filename* read track error: stat=*status*

Explanation

An attempt to read a track from the DASD image named *filename* failed. The status returned was *status*.

Action

Correct the error and retry the operation.

HHCDU005I

HHCDU005I Searching extent 0 begin (*begcyl,beghead*) end (*endcyl,endhead*)

Explanation

The first extent of the dataset is being searched for a key. The extent starts at the track at cylinder *begcyl*, head *beghead*, and ends at the track at cylinder *endcyl*, head *endhead*. This message is only issued if verbose message reporting has been selected.

Action

None.

HHCDU006I

HHCDU006I Searching extent *extent* begin (*begcyl,beghead*) end (*endcyl,endhead*)

Explanation

An extent, *extent*, of the dataset is being searched for a key. The extent starts at the track at cylinder *begcyl*, head *beghead*, and ends at the track at cylinder *endcyl*, head *endhead*. This message is only issued if verbose message reporting has been selected.

Action

None.

HHCDU007E

HHCDU007E Track *track* not found in extent table

Explanation

An attempt was made to convert a track number to an absolute address, but the track specified, *track*, is beyond the end of the dataset.

Action

Correct the error and retry the operation. The dataset, the VTOC, or the DASD image may be corrupt.

HHCDU008E

HHCDU008E Cannot obtain storage for device descriptor buffer: *error*

Explanation

An attempt to obtain storage for the buffer used to hold a CKD DASD image description failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU009E

HHCDU009E Cannot open *filename*: error

Explanation

The CKD image file named *filename* could not be opened. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU010E

HHCDU010E *filename* read error: error

Explanation

An error was encountered while reading the CKD header record from the file named *filename*. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU011E

HHCDU011E *filename* CKD header invalid

Explanation

The file *filename* is not a valid CKD DASD image file. Either the first record is not the length of a CKD header record or the marker in the header record is not correct.

Action

Supply the name of a valid CKD DASD image file and retry the operation.

HHCDU012E

HHCDU012E DASD table entry not found for devtype *type*

Explanation

The device type in the CKD header record does not correspond to any known DASD device. The CKD DASD image file may be corrupt or the device is not supported by Hercules.

Action

Supply the name of a supported CKD DASD image file and retry the operation.

HHCDU013E

HHCDU013E CKD initialization failed for *filename*

Explanation

The device-specific initialization routine for the file named *filename* failed. Another message describes the specific failure.

Action

See the specific message for the action needed.

HHCDU014I

HHCDU014I *filename* heads=*heads* trklen=*trklen*

Explanation

The device represented by the CKD DASD image file named *filename* has *heads* heads and tracks of *trklen* bytes length. This message is only issued if verbose message reporting has been selected.

Action

None.

HHCDU015I

HHCDU015I Updating cyl *cylinder* head *head*

Explanation

During processing of a request to close the CKD image file, the track at cylinder number *cylinder* and head number *head* is being rewritten, since it has been modified. This message is only issued if verbose message reporting has been selected.

Action

None.

HHCDU016E

HHCDU016E *filename* write track error: stat=*status*

Explanation

During processing of a request to close the CKD image file, an attempt to rewrite a track from the DASD image named *filename* failed. The status returned was *status*.

Action

Correct the error and retry the operation.

HHCDU017E

HHCDU017E Cannot obtain storage for device descriptor buffer: *error*

Explanation

An attempt to obtain storage for the buffer used to hold a FBA DASD image description failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU018E

HHCDU018E DASD table entry not found for devtype *type*

Explanation

The default FBA device type does not correspond to any known DASD device. This is likely an internal programming error.

Action

Report the bug to the Hercules development team.

HHCDU019E

HHCDU019E FBA initialization failed for *filename*

Explanation

The device-specific initialization routine for the file named *filename* failed. Another message describes the specific failure.

Action

See the specific message for the action needed.

HHCDU020I

HHCDU020I *filename* sectors=*sectors* size=*size*

Explanation

The device represented by the FBA DASD image file named *filename* has *sectors* sectors of *size* bytes length. This message is only issued if verbose message reporting has been selected.

Action

None.

HHCDU021E

HHCDU021E VOL1 record not found

Explanation

The volume being processed does not have a volume label. It is probably blank and unformatted.

Action

Format the volume or specify a formatted volume and retry the operation.

HHCDU022I

HHCDU022I VOLSER=*serial* VTOC=*cchhr*

Explanation

The volume being processed has the volume serial *serial* and its VTOC format 4 DSCB is at absolute location *cchhr*. This message is only issued if verbose message reporting has been selected.

Action

None.

HHCDU023I

HHCDU023I VTOC start *begcchh* end *endcchh*

Explanation

The VTOC of the volume being processed begins at cylinder and head *begcchh* and ends at cylinder and head *endcchh*. This message is only issued if verbose message reporting has been selected.

Action

None.

HHCDU024E

HHCDU024E Dataset *dsn* not found in VTOC

Explanation

The requested dataset *dsn* was not found in the VTOC and does not exist on this volume.

Action

Specify the correct dataset name or select the volume on which it appears.

HHCDU025I

HHCDU025I DSNAME=*dsn* F1DSCB CCHHR=*cchhr*

Explanation

The format 1 DSCB for the requested dataset *dsn* is at absolute location *cchhr*. This message is only issued if verbose message reporting has been selected.

Action
None.

HHCDU026E

HHCDU026E F1DSCB record not found

Explanation

The requested dataset is listed in the VTOC but its format 1 DSCB record was not found when an attempt was made to read it. The VTOC may be corrupt.

Action

Recreate the dataset and retry the operation.

HHCDU027E

HHCDU027E F3DSCB record not found

Explanation

The requested dataset is reported to contain more than three extents in the format 1 DSCB but its format 3 DSCB record was not found when an attempt was made to read it. The VTOC may be corrupt.

Action

Recreate the dataset and retry the operation.

HHCDU028E

HHCDU028E *filename* open error: *error*

Explanation

An attempt to create the CKD DASD image file named *filename* failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU029E

HHCDU029E *filename* device header write error: *error*

Explanation

An attempt to write the device header to the CKD DASD image file named *filename* failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU030E

HHCDU030E *filename* compressed device header write error: error

Explanation

An attempt to write the compressed device header to the CKD DASD image file named *filename* failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU031E

HHCDU031E Cannot obtain I1tab buffer: error

Explanation

An attempt to obtain storage for the primary lookup table buffer failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU032E

HHCDU032E *filename* primary lookup table write error: error

Explanation

An attempt to write the primary lookup table to the CKD DASD image file named *filename* failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU033E

HHCDU033E *filename* secondary lookup table write error: error

Explanation

An attempt to write the secondary lookup table to the CKD DASD image file named *filename* failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU034E

HHCDU034E *filename* dasdcopy ftruncate error: error

Explanation

An attempt to truncate the CKD DASD image file named *filename* failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU035E

HHCDU035E *filename* cylinder *cyl* head *head* write error: *error*

Explanation

An attempt to write the track at cylinder *cyl*, head *head* to the CKD DASD image file named *filename* failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU036E

HHCDU036E *filename* compressed device header lseek error: *error*

Explanation

An attempt to reposition to the beginning of the CKD DASD image file named *filename* failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU037E

HHCDU037E *filename* compressed device header write error: *error*

Explanation

An attempt to rewrite the compressed device header record of the CKD DASD image file named *filename* failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU038E

HHCDU038E *filename* secondary lookup table lseek error: *error*

Explanation

An attempt to reposition to the secondary lookup table of the CKD DASD image file named *filename* failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU039E

HHCDU039E *filename* secondary lookup table write error: *error*

Explanation

An attempt to rewrite the secondary lookup table of the CKD DASD image file named *filename* failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU040E

HHCDU040E *filename* close error: *error*

Explanation

An attempt to close the CKD DASD image file named *filename* failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU041I

HHCDU041I *count* cylinders successfully written to file *filename*

Explanation

The CKD DASD image file named *filename* has been successfully created. It contains *count* cylinders.

Action

None.

HHCDU042E

HHCDU042E Cylinder count *count* is outside range *min-max*

Explanation

The requested number of cylinders *count* is outside the valid range from *min* to *max*.

Action

Specify a valid number of cylinders and retry the operation.

HHCDU043E

HHCDU043E Cannot obtain track buffer: *error*

Explanation

An attempt to obtain storage for the track buffer failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU044I

HHCDU044I Creating *type* volume *serial*: *cylinders* cyls, *tracks* trks/cyl, *length* bytes/track

Explanation

A new volume is being created of device type *type* and volume serial number *serial*. It has *cylinders* cylinders, *tracks* tracks per cylinder and *length* bytes per track.

Action

None.

HHCDU045E

HHCDU045E Sector count *count* is outside range *min-max*

Explanation

The requested number of sectors *count* is outside the valid range from *min* to *max*.

Action

Specify a valid number of cylinders and retry the operation.

HHCDU046E

HHCDU046E Cannot obtain sector buffer: *error*

Explanation

An attempt to obtain storage for the sector buffer failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU047I

HHCDU047I Creating *type* volume *serial*: *sectors* sectors, *length* bytes/sector

Explanation

A new volume is being created of device type *type* and volume serial number *serial*. It has *sectors* sectors and *length* bytes per sector.

Action

None.

HHCDU048E

HHCDU048E *filename* open error: *error*

Explanation

An attempt to create the FBA DASD image file named *filename* failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU049E

HHCDU049E *filename* dasdcopy ftruncate error: *error*

Explanation

An attempt to truncate the FBA DASD image file named *filename* failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU050E

HHCDU050E *filename* sector *sector* write error: *error*

Explanation

An attempt to write sector number *sector* to the FBA DASD image file named *filename* failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU051E

HHCDU051E *filename* close error: *error*

Explanation

An attempt to close the FBA DASD image file named *filename* failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU052I

HHCDU052I *count* sectors successfully written to file *filename*

Explanation

The FBA DASD image file named *filename* has been successfully created. It contains *count* sectors.

Action
None.

HHCDU053E

HHCDU053E File size too large: *size* [*/1tab*]

Explanation

The requested file size *size* would result in a primary lookup table that is too large. The DASD image cannot be created as a compressed image.

Action

Either specify fewer sectors or create the DASD image uncompressed.

HHCDU054E

HHCDU054E *filename* open error: *error*

Explanation

An attempt to create the compressed FBA DASD image file named *filename* failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU055I

HHCDU055I Creating *type* compressed volume *serial*: *sectors* *sectors*, *length* bytes/sector

Explanation

A new compressed FBA volume is being created of device type *type* and volume serial number *serial*. It has *sectors* sectors and *length* bytes per sector.

Action

None.

HHCDU056E

HHCDU056E *filename* devhdr write error: *error*

Explanation

An attempt to write the device header to the compressed FBA DASD image file named *filename* failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU057E

HHCDU057E *filename* cdevhdr write error: error

Explanation

An attempt to write the compressed device header to the compressed FBA DASD image file named *filename* failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU058E

HHCDU058E *filename* l1tab write error: error

Explanation

An attempt to write the primary lookup table to the compressed FBA DASD image file named *filename* failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU059E

HHCDU059E *filename* l2tab write error: error

Explanation

An attempt to write the secondary lookup table to the compressed FBA DASD image file named *filename* failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU060E

HHCDU060E *filename* block header write error: error

Explanation

An attempt to write a compressed block header to the compressed FBA DASD image file named *filename* failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU061E

HHCDU061E *filename* block write error: error

Explanation

An attempt to write a compressed block to the compressed FBA DASD image file named *filename* failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU062E

HHCDU062E *filename* block write error: error

Explanation

An attempt to write an uncompressed block to the compressed FBA DASD image file named *filename* failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU063E

HHCDU063E *filename* cdevhdr lseek error: error

Explanation

An attempt to reposition to the beginning of the compressed FBA DASD image file named *filename* failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU064E

HHCDU064E *filename* cdevhdr rewrite error: error

Explanation

An attempt to rewrite the compressed device header record of the compressed FBA DASD image file named *filename* failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU065E

HHCDU065E *filename* l2tab lseek error: error

Explanation

An attempt to reposition to the secondary lookup table of the compressed FBA DASD image file named *filename* failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU066E

HHCDU066E *filename* l2tab rewrite error: error

Explanation

An attempt to rewrite the secondary lookup table of the compressed FBA DASD image file named *filename* failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU067E

HHCDU067E *filename* close error: error

Explanation

An attempt to close the compressed FBA DASD image file named *filename* failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCDU068I

HHCDU068I *count* sectors successfully written to file *filename*

Explanation

The compressed FBA DASD image file named *filename* has been successfully created. It contains *count* sectors.

Action

None.

18. Messages HHCHDnnns - Hercules Dynamic Loader

HHCHD001E

HHCHD001E registration alloc failed for *entry*

Explanation

Storage could not be obtained to register entrypoint *entry*

Action

Correct the error and restart Hercules.

HHCHD002E

HHCHD002E cannot allocate memory for DLL descriptor: *error*

Explanation

Initialisation of the dynamic loader environment failed due to the error described by *error*.

Action

Correct the error and restart Hercules.

HHCHD003E

HHCHD003E unable to open Hercules as DLL: *error*

Explanation

The main Hercules load module could not be opened by the dynamic loader. The dynamic loader error is described by *error*

Action

Correct the error and restart Hercules.

HHCHD004I

HHCHD004I No initializer in *module*: *error*

Explanation

The initializer in DLL named *module* could not be found. The error is described by *error*

Action

Correct the error and restart Hercules.

HHCHD005E

HHCHD005E *module already loaded.*

Explanation

An attempt was made to load an already loaded module.

Action

Unload to module first.

HHCHD006S

HHCHD006S cannot allocate memory for DLL descriptor: *error*

Explanation

Initialisation of the dynamic loader environment failed due to the error described by *error*.

Action

Correct the error and restart Hercules.

HHCHD007E

HHCHD007E unable to open DLL *module*: *error*

Explanation

The DLL named *module* could not be opened. The error is described by *error*.

Action

Ensure that the correct module is specified and is accessible.

HHCHD008I

HHCHD008I No initializer in *module*: *error*

Explanation

The initializer in DLL named *module* could not be found. The error is described by *error*

Action

Correct the error and restart Hercules.

HHCHD009E

HHCHD009E *module not found*

Explanation

An attempt was made to unload a module that was not loaded.

Action

No action required.

HHCHD010I

HHCHD010I Dependency check failed for *module*, version(*vers_actual*) expected(*vers_exp*)

Explanation

The version of the module's required dependency does not match the version of the dependency in the module that contains the dependency.

Action

No action required.

HHCHD011I

HHCHD011I Dependency check failed for *module*, size(*size_actual*) expected(*size_exp*)

Explanation

The size of the modules required dependency does not match the size of the dependency in the module that contains the dependency.

Action

No action required.

HHCHD012E

HHCHD012E No dependency section in *module*: *error*

Explanation

The module being loaded does not contain the required dependency section. The error is described by *error*.

Action

Rebuild the module with the required HDL_DEPENDENCY_SECTION defined.

HHCHD013E

HHCHD013E No dependency section in *module*: *error*

Explanation

The module being loaded does not contain the required dependency section. The error is described by *error*.

Action

Rebuild the module with the required HDL_DEPENDENCY_SECTION defined.

HHCHD014E

HHCHD014E Dependency check failed for module *module*

Explanation

One or more required dependencies were not satisfied. The preceding HHCHD010I and/or HHCHD011I message(s) identifies which of the dependencies failed and the reason why.

Action

If the module was not loaded, rebuild the module using the same version of the required dependency as the module that contains the dependency and try again.

HHCHD015E

HHCHD015E Unloading of *module* not allowed

Explanation

An attempt was made to unload a module that was not allowed to be unloaded.

Action

No action required.

HHCHD018I

HHCHD018I Loadable module directory is *dir*

Explanation

The default loadable module directory was manually changed to *dir* via either a supplied MODPATH configuration file statement or via the -d command line option.

Action

No action required.

HHCHD100I

HHCHD100I Loading *module* ...

Explanation

Module *module* is being loaded.

Action

No action required.

HHCHD101I

HHCHD101I Module *module* loaded

Explanation

Module *module* has been loaded.

Action

No action required

HHCHD102I

HHCHD102I Unloading *module* ...

Explanation

Module *module* is being unloaded.

Action

No action required

HHCHD103I

HHCHD103I Module *module* unloaded

Explanation

Module *module* has been unloaded.

Action

No action required

19. Messages HHCHEnns - HETINIT Utility

HHCHEnns

Messages HHCHEnns are not yet documented.

20. Messages HHCHGnnns - HETGET Utility

HHCHGnnns

Messages HHCHGnnns are not yet documented.

21. Messages HHCHMnnns - HETMAP Utility

HHCHMnnns

Messages HHCHMnnns are not yet documented.

22. Messages HHCHTnnns - HTTP Server

HHCHT001I

HHCHT001I HTTP listener thread started: tid=*threadid*, pid=*processid*

Explanation

The HTTP server thread to accept and process incoming requests has been started. The thread id is *threadid* and the process id is *processid*.

Action

No action required.

HHCHT002E

HHCHT002E socket: *error*

Explanation

An attempt to obtain a TCP socket to receive HTTP requests failed. The error is described by *error*.

Action

Correct the error and restart Hercules.

HHCHT003W

HHCHT003W Waiting for port *port* to become free

Explanation

The thread that handles HTTP connection requests is waiting for the TCP port denoted by *port* to become available for use.

Action

If this message persists, some other program has control of the TCP port listed. Find out which one it is and terminate it.

HHCHT004E

HHCHT004E bind: *error*

Explanation

An attempt to bind the socket to the TCP port to receive HTTP requests failed. The error is described by *error*.

Action

Correct the error and restart Hercules.

HHCHT005E

HHCHT005E listen: *error*

Explanation

An attempt to put the socket into listening state for HTTP requests failed. The error is described by *error*.

Action

Correct the error and restart Hercules.

HHCHT006I

HHCHT006I Waiting for HTTP requests on port *port* pid=*num*

Explanation

Hercules is ready to accept HTTP requests on port *port*.

Action

No action required.

HHCHT007E

HHCHT007E select: *error*

Explanation

An attempt to wait for data from HTTP requests failed. The error is described by *error*.

Action

Correct the error and restart Hercules.

HHCHT008E

HHCHT008E accept: *error*

Explanation

An attempt to accept a TCP connection for HTTP requests failed. The error is described by *error*.

Action

Correct the error and restart Hercules.

HHCHT009E

HHCHT009E fdopen: *error*

Explanation

An attempt to open the socket for reading HTTP requests failed. The error is described by *error*.

Action

Correct the error and restart Hercules.

HHCHT010E

HHCHT010E http_request create_thread: *error*

Explanation

An attempt to create a thread for processing HTTP requests failed. The error is described by *error*.

Action

Correct the error and restart Hercules.

HHCHT011E

HHCHT011E html_include: Cannot open *filename*: *error*

Explanation

The file named *filename*, which was included from another file, could not be opened. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCHT014I

HHCHT014I HTTPROOT = *pathname*

Explanation

The root directory path for the HTTP server is *pathname*.

Action

No action required.

23. Messages HHCHUnnns - HETUPD Utility

HHCHUnnns

Messages HHCHUnnns are not yet documented.

24. Messages HHCIFnnns - Network Interface Configuration Handler (hercific)

HHCIF001E

HHCIF001E *programname*: Must be called from within Hercules.

Explanation

This program can only be called from Hercules itself and may not be executed from the command line. The program was executed using the name *programname*.

Action

Don't do that.

HHCIF002E

HHCIF002E *programname*: Cannot obtain socket: *error*

Explanation

An attempt to obtain a socket for controlling the destination interface failed. The error is described by *error*. The program was executed using the name *programname*.

Action

Correct the error and retry the operation.

HHCIF003E

HHCIF003E *programname*: I/O error on read: *error*

Explanation

An attempt to read a request from Hercules failed. The error is described by *error*. The program was executed using the name *programname*.

Action

Correct the error and retry the operation.

HHCIF004W

HHCIF004W *programname*: Unknown request: *request*.

Explanation

The request from Hercules was invalid. The request code was *request*. The request has been ignored. The program was executed using the name *programname*.

Action

Make sure that the hercific program is the same version as the running copy of Hercules. If so, this is an internal error. Report it.

HHCIF005E

HHCIF005E *programname*: ioctl error doing *operation* on *interface*: *error*

Explanation

An attempt to perform an ioctl operation *operation* on interface *interface* failed. The error is described by *error*. The program was executed using the name *programname*.

Action

Correct the error and retry the operation.

25. Messages HHCINnnns - Hercules Initialization

HHCIN001S

HHCIN001S Cannot register SIGINT handler: *error*

Explanation

An attempt to register a handler for the SIGINT signal failed. The error is described by *error*.

Action

Correct the error and restart Hercules.

HHCIN002E

HHCIN002E Cannot suppress SIGPIPE signal: *error*

Explanation

An attempt to ignore the SIGPIPE signal failed. The error is described by *error*. This will cause Hercules to terminate abnormally if a printer device is defined to a pipe and that pipe is closed while data is being written to it.

Action

Correct the error and restart Hercules. Do not print to a pipe until you have corrected the error.

HHCIN003S

HHCIN003S Cannot register SIGILL/FPE/SEGV/BUS/USR handler: *error*

Explanation

An attempt to register a handler for one of the listed signals failed. The error is described by *error*.

Action

Correct the error and restart Hercules.

HHCIN004S

HHCIN004S Cannot create watchdog thread: *error*

Explanation

An attempt to create the watchdog thread to monitor Hercules execution failed. The error is described by *error*.

Action

Correct the error and restart Hercules.

HHCIN005S

HHCIN005S Cannot create http_server thread: error

Explanation

An attempt to create the HTTP server thread failed. The error is described by *error*.

Action

Correct the error and restart Hercules.

HHCIN006S

HHCIN006S Cannot create panel thread: error

Explanation

An attempt to create the operator control panel thread failed. The error is described by *error*.

Action

Correct the error and restart Hercules.

HHCIN007S

HHCIN007S Cannot create devnum connection thread: error

Explanation

The shared device server was unable to create the thread meant to manage remote device *devnum*. The error is described by *error*.

Action

Correct the error and restart Hercules.

HHCIN008S

HHCIN008S DYNGUI.DLL load failed; Hercules terminated.

Explanation

The external GUI interface module 'dyngui.dll' could not loaded. The preceding HHCHD007E message should provide the reason for the failure.

Action

Correct the error and restart Hercules. If the error is Win32 error 126 ("The specified module could not be found"), check your Windows PATH setting and/or your MODPATH control statement to ensure one or both of them includes the directory where Hercules is executing from.

HHCIN099I

HHCIN099I Hercules terminated

Explanation

Hercules has ended.

Action

No action required.

26. Messages HHCLCnnns - LCS Emulation

HHCLC001E

HHCLC001E *nnnn* unable to allocate LCSBLK

Explanation

There is insufficient storage to allocate the control block for LCS device number *nnnn*.

Action

Correct the error and restart Hercules.

HHCLC017E

HHCLC017E *nnnn* invalid device name *devname*

Explanation

The value of the -n or -dev parameter in the configuration statement for LCS device number *nnnn* is missing or too long.

Action

Correct the parameter and reinitialize the device.

HHCLC018E

HHCLC018E *nnnn* invalid MAC address *macaddr*

Explanation

The value of the -m or -mac parameter in the configuration statement for LCS device number *nnnn* is not a valid MAC address.

Action

Correct the parameter and reinitialize the device.

HHCLC019E

HHCLC019E *nnnn* too many arguments in statement

Explanation

The configuration statement for LCS device number *nnnn* contains too many positional parameters.

Action

Correct the statement and restart Hercules.

HHCLC020E

HHCLC020E *nnnn* invalid IP address *ipaddr*

Explanation

The first positional parameter in the configuration statement for LCS device number *nnnn* is not a valid IP address.

Action

Correct the statement and reinitialize the device.

HHCLC021E

HHCLC021E Invalid HWADD statement in *filename: stmt*

Explanation

The port number parameter of the HWADD statement *stmt* in OAT file *filename* is not numeric.

Action

Correct the statement and reinitialize the device.

HHCLC022E

HHCLC022E Invalid MAC in HWADD statement in *filename: stmt (macaddr)*

Explanation

The second positional parameter of the HWADD statement *stmt* in OAT file *filename* is not a valid MAC address.

Action

Correct the parameter and reinitialize the device.

HHCLC023E

HHCLC023E Invalid ROUTE statement in *filename: stmt*

Explanation

The port number parameter of the ROUTE statement *stmt* in OAT file *filename* is not numeric.

Action

Correct the statement and reinitialize the device.

HHCLC024E

HHCLC024E Invalid net address in ROUTE *filename: stmt (netaddr)*

Explanation

The second positional parameter of the ROUTE statement *stmt* in OAT file *filename* is not a valid IP network address.

Action

Correct the parameter and reinitialize the device.

HHCLC025E

HHCLC025E Invalid net mask in ROUTE *filename: stmt (netaddr)*

Explanation

The third positional parameter of the ROUTE statement *stmt* in OAT file *filename* is not a valid IP network mask.

Action

Correct the parameter and reinitialize the device.

HHCLC026E

HHCLC026E Error in *filename*: Missing device number or mode

Explanation

The OAT file *filename* contains a statement which cannot be identified.

Action

Correct the statement and reinitialize the device.

HHCLC027E

HHCLC027E Error in *filename: devnum*: Invalid device number

Explanation

The device number *devnum* specified in the OAT file *filename* is not a valid hexadecimal number.

Action

Correct the statement and reinitialize the device.

HHCLC028E

HHCLC028E Error in *filename: stmt*: Missing PORT number

Explanation

Statement *stmt* in OAT file *filename* for the IP port of an LCS device does not contain a port number.

Action

Correct the statement and reinitialize the device.

HHCLC029E

HHCLC029E Error in *filename: port*: Invalid PORT number

Explanation

The port number *port* specified in the OAT file *filename* for the IP port of an LCS device is not a valid decimal number.

Action

Correct the statement and reinitialize the device.

HHCLC031E

HHCLC031E Error in *filename: stmt*: Invalid entry starting at *text*

Explanation

The parameter *text* specified in statement *stmt* in the OAT file *filename* should be PRI, SEC, or NO.

Action

Correct the statement and reinitialize the device.

HHCLC032E

HHCLC032E Error in *filename: stmt*: Invalid IP address (*ipaddr*)

Explanation

The parameter *ipaddr* specified in statement *stmt* in the OAT file *filename* is not a valid IP address.

Action

Correct the statement and reinitialize the device.

HHCLC033E

HHCLC033E Error in *filename: stmt*: Missing PORT number

Explanation

Statement *stmt* in OAT file *filename* for the SNA port of an LCS device does not contain a port number.

Action

Correct the statement and reinitialize the device.

HHCLC034E

HHCLC034E Error in *filename: port*: Invalid PORT number

Explanation

The port number *port* specified in the OAT file *filename* for the SNA port of an LCS device is not a valid decimal number.

Action

Correct the statement and reinitialize the device.

HHCLC035E

HHCLC035E Error in *filename: stmt*: SNA does not accept any arguments

Explanation

Statement *stmt* in OAT file *filename* for the SNA port of an LCS device contains positional parameters which are not used for SNA ports.

Action

Correct the statement and reinitialize the device.

HHCLC036E

HHCLC036E Error in *filename: mode: Invalid MODE*

Explanation

Mode *mode* specified in a device statement in the OAT file *filename* should be IP or SNA.

Action

Correct the statement and reinitialize the device.

HHCLC037E

HHCLC037E Error reading file *filename* line *nnnn: description*

Explanation

An error occurred reading the OAT file for an LCS device. *description* is the operating system's description of the error. The error occurred at line *nnnn* of file *filename*.

Action

Check that the correct OAT file name is specified in the configuration file.

HHCLC038E

HHCLC038E File *filename* line *nnnn* is too long

Explanation

An error occurred reading the OAT file for an LCS device. The error occurred at line *nnnn* of file *filename*. Either the line exceeds 255 characters, or there is no linefeed at the end of the file.

Action

Correct the OAT file.

HHCLC039E

HHCLC039E Cannot open file *filename: description*

Explanation

An error occurred opening the OAT file *filename* for an LCS device. *description* is the operating system's description of the error.

Action

Check that the correct OAT file name is specified in the configuration file.

HHCLC040E

HHCLC040E *nnnn* LCSDEV *mmmm* not in configuration

Explanation

The device number *mmmm* specified in the OAT file does not match the LCS device number *nnnn* in the configuration file.

Action
None.

HHCLC055I

HHCLC055I *tapn* using MAC *hh:hh:hh:hh:hh:hh*

Explanation

The MAC address assigned the TUN/TAP device *tapn* is *hh:hh:hh:hh:hh:hh*.

Action

Correct the OAT file and reinitialize the device.

HHCLC056W

HHCLC056W *tapn* NOT using MAC *hh:hh:hh:hh:hh:hh*

Explanation

MAC address *hh:hh:hh:hh:hh:hh* was requested in the configuration statement or in the OAT file for an LCS device but the operating system did not accept the request to change the MAC address for TUN/TAP device *tapn*.

Action

The device will use the MAC address shown in the preceding HHCLC055I message.

HHCLC073I

HHCLC073I *nnnn*: TAP device *tapn* opened

Explanation

LCS device number *nnnn* is now associated with the kernel TUN/TAP device named *tapn*.

Action

None.

27. Messages HHCLGnnns - System Log Functions

HHCLG001E

HHCLG001E Error redirecting stdout: *error*

Explanation

The stdout stream could not be redirected to the system logger. The error is described by *error*.

HHCLG002E

HHCLG002E Error reading syslog pipe: *error*

Explanation

An error occurred while reading the syslog pipe. The error is described by *error*.

HHCLG003E

HHCLG003E Error writing hardcopy log: *error*

Explanation

The error as indicated by *error* occurred while writing the hardcopy log.

HHCLG004E

HHCLG004E Error duplicating stderr: *error*

Explanation

Stdout could not be redirected to stderr. The error is described by *error*.

HHCLG005E

HHCLG005E Error duplicating stdout: *error*

Explanation

Stderr could not be redirected to stdout. The error is described by *error*.

HHCLG006E

HHCLG006E Duplicate error redirecting hardcopy log: *error*

Explanation

The error described by *error* occurred whilst redirecting the hardcopy log.

HHCLG007S

HHCLG007S Hardcopy log fdopen failed: *error*

Explanation

An attempt to open a stream for the hardcopy log failed. The error is described by *error*.

HHCLG008S

HHCLG008S logbuffer malloc failed: *error*

Explanation

An instorage buffer for the system log could not be obtained. The error is described by *error*.

HHCLG009S

HHCLG009S Syslog message pipe creation failed: *error*

Explanation

An attempt to create the pipe for the system logger failed. The error is described by *error*.

Action

Check that your firewall is not preventing Hercules from opening a listening pipe.

HHCLG012E

HHCLG012E Cannot create logger thread: *error*

Explanation

An attempt to create the logger thread failed. *Error* is the description of the error code returned by the `pthread_create` call.

Action

If the error is "No error" ensure that Hercules has been correctly linked with the pthread library.

HHCLG014E

HHCLG014E Log not active

Explanation

A *log off* command was issued but there was no active log file.

Action

None.

HHCLG015I

HHCLG015I Log closed

Explanation

The active log file has been closed as a result of a *log off* command.

Action

None.

HHCLG016E

HHCLG016E Error opening log file *filename: error*

Explanation

The new log file requested by a *log* command could not be opened. *error* is the description of the error code returned by the open call.

Action

Reissue the *log* command with the correct filename.

HHCLG017S

HHCLG017S Log file fdopen failed for *filename: error*

Explanation

The logger was unable to obtain the file descriptor for the new log file requested by a *log* command. *error* is the description of the error code returned by the fdopen call.

Action

Reissue the *log* command with the correct filename.

HHCLG018I

HHCLG018I Log switched to *filename*

Explanation

As a result of a *log* command the logger is now writing to the requested log file.

Action

None.

28. Messages HHCPNnnns - Control Panel Command Messages

HHCPN001I

HHCPN001I Control panel thread started: tid=*threadid*, pid=*processid*

Explanation

The control panel thread has been started. Its thread id is *threadid* and its process id is *processid*.

Action

No action required.

HHCPN002S

HHCPN002S Cannot obtain keyboard buffer: *error*

Explanation

An attempt to obtain memory for the keyboard buffer, used to hold operator input, failed. The error is described by *error*.

Action

Correct the error and restart Hercules.

HHCPN003S

HHCPN003S Cannot obtain message buffer: *error*

Explanation

An attempt to obtain memory for the message buffer, used to hold operator output, failed. The error is described by *error*.

Action

Correct the error and restart Hercules.

HHCPN004E

HHCPN004E select: *error*

Explanation

An error was encountered while waiting for input from the console. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCPN005E

HHCPN005E keyboard read: *error*

Explanation

An error was encountered while attempting to read keyboard input. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCPN006E

HHCPN006E message pipe read: *error*

Explanation

An error was encountered while attempting to read from the pipe used to communicate to the control panel thread from the rest of Hercules. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCPN007E

HHCPN007E RC file *filename* open failed: *error*

Explanation

The RC file containing commands to be executed at Hercules startup, named *filename*, could not be opened. The error is described by *error*.

Action

Correct the error and restart Hercules if necessary. The commands contained in the file may be issued manually.

HHCPN008I

HHCPN008I RC file processing thread started using file *filename*

Explanation

Processing of the commands contained in the file named *filename* has begun.

Action

No action required.

HHCPN009E

HHCPN009E RC file buffer malloc failed: *error*

Explanation

An attempt to obtain storage for the buffer for commands being read from the startup command file failed. The error is described by *error*.

Action

Correct the error and restart Hercules, if needed. The comands contained in the file may be issued manually.

HHCPN010W

HHCPN010W Ignoring invalid RC file pause statement: *argument*

Explanation

The argument *argument* on the pause statement in the startup command file is invalid. It must be a decimal number between 0 and 999. Processing will continue without any pause.

Action

Correct the invalid argument and restart Hercules, if desired.

HHCPN011I

HHCPN011I Pausing RC file processing for *delay* seconds...

Explanation

Processing of the startup command file is being delayed for *delay* seconds because of a pause statement in the file.

Action

No action required.

HHCPN012I

HHCPN012I Resuming RC file processing...

Explanation

Processing of the startup command file has resumed at the expiration of the delay interval.

Action

No action required.

HHCPN013I

HHCPN013I EOF reached on RC file. Processing complete.

Explanation

The end of the startup command file has been reached and processing of the file is complete.

Action

No action required.

HHCPN014E

HHCPN014E I/O error reading RC file: *error*

Explanation

An error was encountered while reading a command from the startup command file. The error is described by *error*. Any remaining commands in the file will not be processed.

Action

Correct the error and restart Hercules if desired. Any unprocessed commands may be issued manually.

HHCPN052E

HHCPN052E Target CPU *nnnn* type *cputype* does not allow ipl

Explanation

An IPL command was issued but the target CPU *nnnn* is a processor engine of type *cputype* which does not support the initial program load procedure.

Action

Use the CPU command to set the target CPU to a processor of type CP, IFL, or ICF, then re-issue the IPL command.

HHCPN162I

HHCPN162I Hercules instruction trace displayed in { *regsfirst* | *noregs* | *traditional* } mode

Explanation

This message shows the current setting of the traceopt mode.

Action

None.

HHCPN180E

HHCPN180E 'sh' commands are disabled

Explanation

The 'sh' (shell) command has been purposely disabled via a SHCMDOPT configuration file statement. Shell commands entered via the Hercules hardware console will not be processed.

Action

Remove or modify the SHCMDOPT configuration file statement and restart Hercules.

HHCPN181E

HHCPN181E Device number s:CCUU not found

Explanation

The device number "CCUU" on Logical Channel Subsystem "s" was not found in the configuration.

Action

Reissue the command with an existing device number.

HHCPN195I

HHCPN195I Log options: *val*

Explanation

This message displays the current logging options. It is issued when the LOGOPT command is entered without operands. *val* is `TIMESTAMP` or `NOTIMESTAMP`.

Action

None.

HHCPN196E

HHCPN196E Invalid logopt value *val*

Explanation

This message is issued when the operand of a LOGOPT command is an invalid value. Valid values for *val* are `TIMESTAMP` or `NOTIMESTAMP`.

Action

Reenter the LOGOPT command with a valid operand.

HHCPN197I

HHCPN197I Log option set: *val*

Explanation

As the result of the LOGOPT command, the Hercules logging option *val* has been set. *val* is `TIMESTAMP` or `NOTIMESTAMP`.

Action

None.

29. Messages HHCPRnnns - Printer Emulation

HHCPR001E

HHCPR001E File name missing or invalid for printer *address*

Explanation

There was no file name specified for the printer at address *address*, or else there was one specified but it was too long.

Action

Correct the error in the Hercules configuration file. The device may be made available by specifying a filename with the devinit command.

HHCPR002E

HHCPR002E Invalid argument for printer *address: argument*

Explanation

An invalid argument was specified on the definition of the printer at address *address*.

Action

Correct or remove the invalid argument.

HHCPR003E

HHCPR003E *address* Error writing to *filename: error*

Explanation

An error was encountered when writing output for the printer at address *address* to the file named *filename*. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCPR004E

HHCPR004E Error opening file *filename: error*

Explanation

An error was encountered when opening the file named *filename*. The error is described by *error*.

Action

Correct the error and retry the operation.

HH CPR005E

HH CPR005E *address device initialization error: pipe: error*

Explanation

An error was encountered when opening a pipe for the printer at address *address*. The error is described by *error*.

Action

Correct the error and retry the operation.

HH CPR006E

HH CPR006E *address device initialization error: fork: error*

Explanation

An error was encountered when starting the program to process the output from the printer at address *address*. The error is described by *error*.

Action

Correct the error and retry the operation.

HH CPR007I

HH CPR007I *pipe receiver (pid=*processid*) starting for *address**

Explanation

The program to process the output from the printer at address *address* is starting. Its process id is *processid*.

Action

No action required.

HH CPR008E

HH CPR008E *address dup2 error: error*

Explanation

The file descriptor for stdin could not be duplicated for the program to process the output from the printer at address *address*. The error is described by *error*.

Action

Correct the error and retry the operation.

HH CPR009E

HH CPR009E *address dup2 error: error*

Explanation

The file descriptor for stdout could not be duplicated for the program to process the output from the printer at address *address*. The error is described by *error*.

Action

Correct the error and retry the operation.

HH CPR010E

HH CPR010E *address dup2 error: error*

Explanation

The file descriptor for stderr could not be duplicated for the program to process the output from the printer at address *address*. The error is described by *error*.

Action

Correct the error and retry the operation.

HH CPR011I

HH CPR011I pipe receiver (pid=*processid*) terminating for *address*

Explanation

The program to process the output from the printer at address *address* has ended successfully. Its process id was *processid*.

Action

No action required.

HH CPR012E

HH CPR012E *address Unable to execute program: error*

Explanation

The program named *program* to process the output from the printer at address *address* could not be started. The error is described by *error*.

Action

Correct the error and retry the operation.

30. Messages HHCPUnnns - Card Punch Emulation

HHCPU001E

HHCPU001E File name missing or invalid

Explanation

The file name specified for punched output is invalid or no file name is given.

Action

Correct the error and retry the operation.

HHCPU002E

HHCPU002E Invalid argument: *argument*

Explanation

An invalid argument *argument* was specified for the card punch. Valid arguments are ascii, ebclic, and crlf.

Action

Correct the invalid argument and retry the operation.

HHCPU003E

HHCPU003E Error opening file *filename: error*

Explanation

The file named *filename* could not be opened for output of card punch data. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCPU004E

HHCPU004E Error writing to *filename: error*

Explanation

The file named *filename* encountered an error while writing card punch data. The error is described by *error*.

Action

Correct the error and retry the operation.

31. Messages HHCRDnnns - Card Reader Emulation

HHCRD001E

HHCRD001E Out of memory

Explanation

A request to allocate memory for the list of files to be read failed.

Action

Correct the error and retry the operation.

HHCRD002E

HHCRD002E File name too long (max=*max*): "*filename*"

Explanation

The file name specified by *filename* is too long. The maximum length is *max*.

Action

Specify a shorter name.

HHCRD003E

HHCRD003E Unable to access file "*filename*": *error*

Explanation

The file specified by *filename* could not be accessed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCRD004E

HHCRD004E Out of memory

Explanation

A request to allocate memory for the list of files to be read failed.

Action

Correct the error and retry the operation.

HHCRD005E

HHCRD005E Specify 'ascii' or 'ebcdic' (or neither) but not both

Explanation

Both of the character set translation options `ascii` and `ebcdic` were specified. At most one is allowed.

Action

Select only one character set translation option.

HHCRD006E

HHCRD006E Only one filename (`sock_spec`) allowed for socket devices

Explanation

More than one filename argument was given for a socket card reader device. Only one is allowed. This error can also result if an option name is misspelled.

Action

Remove the extraneous filenames or correct the misspelled options.

HHCRD007I

HHCRD007I Defaulting to 'ascii' for socket device *address*

Explanation

The socket card reader device at address *address* has been set to ASCII mode since neither translation option was specified. The socket card reader device cannot automatically select the translation option.

Action

If you wish to read cards without translation from ASCII to EBCDIC, you must specify the `ebcdic` option on the reader definition.

HHCRD008W

HHCRD008W 'multifile' option ignored: only one file specified

Explanation

Only one file was specified for input to the card reader and the `multifile` option was specified. This option is Explanationless with only one input file. The option has been ignored.

Action

If you wish to read more than one input file without signalling end-of-file or intervention required between them, then all files must all be specified on the same reader definition. If you only wish to process one file, omit the `multifile` option.

HHCRD009E

HHCRD009E File name too long (max=*max*): "*filename*"

Explanation

The file name specified by *filename* is too long. The maximum length is *max*.

Action

Specify a shorter name.

HHCRD010E

HHCRD010E Unable to access file "*filename*": *error*

Explanation

The file specified by *filename* could not be accessed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCRD011E

HHCRD011E Close error on file "*filename*": *error*

Explanation

An attempt to close the file specified by *filename* failed. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCRD012I

HHCRD012I *ipaddr* (*hostname*) disconnected from device *address* (*socketspec*)

Explanation

The client on the host named *hostname*, with the IP address *ipaddr*, has disconnected from the socket card reader device at address *address*, specified by *socketspec*.

Action

No action required.

HHCRD013E

HHCRD013E Error opening file *filename*: *error*

Explanation

The file named *filename* could not be opened for reading. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCRD014E**HHCRD014E Error reading file *filename*: error****Explanation**

An error was encountered while attempting to read the first 160 bytes of the file named *filename* in order to determine its character set. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCRD015E**HHCRD015E Seek error in file *filename*: error****Explanation**

An error was encountered while attempting to return to the beginning of file named *filename* after determining its character set. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCRD016E**HHCRD016E Error reading file *filename*: error****Explanation**

An error was encountered while attempting to read an EBCDIC card image from the file named *filename*. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCRD017E**HHCRD017E Unexpected end of file on *filename*****Explanation**

Too few characters were read from the file named *filename*. The autopad option was not specified.

Action

Either ensure that all records in the file are 80 bytes long, or specify the autopad option on the reader definition.

HHCRD018E

HHCRD018E Error reading file *filename*: *error*

Explanation

An error was encountered while attempting to read an ASCII card image from the file named *filename*. The error is described by *error*.

Action

Correct the error and retry the operation.

HHCRD019E

HHCRD019E Card image exceeds *size* bytes in file *filename*

Explanation

A line in the file named *filename* is too long to fit on one card. The trunc option was not specified. The maximum length is *size* bytes.

Action

Either ensure that all lines in the file are less than *size* bytes long or specify the trunc option on the reader definition.

32. Messages HHCSDnnns - Socket Devices Common Functions

HHCSDnnns

Messages HHCSDnnns are not yet documented.

33. Messages HHCTAnnns - Tape Device Emulation

HHCTAnnns

Messages HHCTAnnns are not yet documented.

34. Messages HHCTCnnns - TAPECOPY Utility

HHCTCnnns

Messages HHCTCnnns are not yet documented.

35. Messages HHCTEnns - Terminal Emulation

HHCTE001I

HHCTE001I Console connection thread started: tid=*threadid*, pid=*processid*

Explanation

The thread that handles connection requests from console devices has been started.

Action

No action required.

HHCTE002W

HHCTE002W Waiting for port *port* to become free

Explanation

The thread that handles connection requests from console devices is waiting for the TCP port denoted by *port* to become available for use.

Action

If this message persists, some other program has control of the TCP port listed. Determine the program involved and terminate it.

HHCTE003I

HHCTE003I Waiting for console connection on port *port* pid=*num*

Explanation

Hercules is ready to accept console connections on port *port*.

Action

No action required.

HHCTE004I

HHCTE004I Console connection thread terminated

Explanation

The thread that handles connection requests from console devices has been terminated.

Action

No action required.

HHCTE005E

HHCTE005E Cannot create console thread: *reason*

Explanation

The thread that handles connection requests from console devices could not be started. The reason is shown as *reason*.

Action

Correct the reason listed and restart Hercules.

HHCTE006A

HHCTE006A Enter input for console device *address*

Explanation

The 1052 console device at *address* is waiting for input.

Action

Type the desired input for the console and press the ENTER key. If you do not wish to get this message when input is requested, define the console with the option `noprompt`.

HHCTE007I

HHCTE007I Device *address* closed by client *ipaddr*

Explanation

The client at IP address *ipaddr* that was connected to the 3270 console at address *address* has closed the connection. The device is no longer available for use.

Action

No action required.

HHCTE008I

HHCTE008I Device *address* closed by client *ipaddr*

Explanation

The client at IP address *ipaddr* that was connected to the 1052 console at address *address* has closed the connection. The device is no longer available for use.

Action

No action required.

HHCTE009I

HHCTE009I Client *ipaddr* connected to *type* device *address*

Explanation

The client at IP address *ipaddr* has connected to Hercules as a *type* device and is now available at address *address*.

Action

No action required.

HHCTE010E

HHCTE010E CNSLPORT statement invalid: *statement*

Explanation

The CNSLPORT statement in the Hercules configuration file is invalid.

Action

Correct the CNSLPORT statement in the configuration file and restart Hercules.

HHCTE011E

HHCTE011E Device *devn*: Invalid IP address: *ipaddr*

Explanation

The IP address *ipaddr* is invalid.

Action

Correct the IP address in the configuration file and restart Hercules.

HHCTE012E

HHCTE012E Device *devn*: Invalid mask value: *ipmask*

Explanation

The mask value *ipmask* is invalid.

Action

Correct the mask value in the configuration file and restart Hercules.

HHCTE013E

HHCTE013E Device *devn*: Extraneous argument(s): *xxx...*

Explanation

The argument(s) *xxx* and any which follow it (if any) was not recognized or understood and are thus invalid.

Action

Correct the arguments in the configuration file and restart Hercules.

HHCTE014I

HHCTE014I *type device devn disconnected.*

Explanation

The client connected to device *devn* has abruptly terminated the connection (ECONNRESET).

Action

No action required.

HHCTE017E

HHCTE017E Device *devn*: Duplicate SYSG console definition.

Explanation

Device number *devn* has been defined as an integrated 3270 (SYSG) console, but a SYSG console already exists. Only one SYSG console can be defined per system.

Action

Correct the statement in the configuration file and restart Hercules.

36. Messages HHCTMnnns - TAPEMAP Utility

HHCTMnnns

Messages HHCTMnnns are not yet documented.

37. Messages HHCTSnnns - TAPESPLT Utility

HHCTSnnns

Messages HHCTSnnns are not yet documented.

38. Messages HHCTTnnns - TOD Clock and Timer Services

HHCTT001W

HHCTT001W Timer thread set priority *priority* failed: *error*

Explanation

An attempt to change the priority of the timer thread to *priority* failed. The error is described by *error*. The thread priority has not been changed. Hercules overall performance may be impaired as a result.

Action

If performance problems are noted, correct the error and restart Hercules.

HHCTT002I

HHCTT002I Timer thread started: tid=*threadid*, pid=*processid*, priority=*priority*

Explanation

The thread for timing functions has been started. Its thread id is *threadid*, its process id is *processid* and the thread priority is *priority*.

Action

No action required.

HHCTT003I

HHCTT003I Timer thread ended

Explanation

The thread for timing functions has ended.

Action

No action required.

39. Messages HHCTUnnns - TUN / TAP Driver Support

HHCTUnnns

Messages HHCTUnnns are not yet documented.

40. Messages HHCVMnnns - VM / CP Emulation

HHCVM001I

HHCVM001I **panel_command** panel command Module guest

Explanation

The guest operating system has issued a DIAGNOSE 8 instruction to perform the *panel_command* panel command to be carried out by the Hercules panel command processor

System Action

The Hercules panel command processor carries out the command if possible.

Operator Action

None

Programmer Action

No action is requested if this behaviour is expected. If this behaviour poses a security concern, the *DIAG8CMD* configuration statement should either be omitted or specified with the *disabled* argument.

HHCVM002I

HHCVM002I **panel_command* command complete

Explanation

The *panel_command* panel command has been carried out by the panel command processor. Note that this message only appears if the guest issued diagnose 8 instruction specified that it did not request the command response to be placed in a supplied buffer.

System Action

The system continues

Operator Action

None. This is an informational message

Programmer Action

None. This is an informational message

HHCVM003I

HHCVM003I Host command processing disabled by configuration statement

Explanation

The guest operating system attempted using the DIAGNOSE 8 Instruction to carry out a panel command, but the system configuration disabled this feature (with the *DIAG8CMD* configuration statement)

System Action

The panel command is ignored.

Operator Action

None.

Programmer Action

If it is deemed necessary for the guest operating system to issue DIAGNOSE 8 commands to issue panel commands, the *DIAG8CMD* with the *enable* argument should be specified in the configuration file.

HHCVM004E**HHCVM004E Host command processing not included in engine build****Explanation**

The Hercules engine has been built without Diagnose 8 panel command facility support

System Action

The panel command is not issued. The system continues.

Operator Action

None

Programmer Action

If it is desired that DIAGNOSE 8 Instruction be carried out as panel commands, the facility should be included in the build process. Additionally, the *DIAG8CMD* configuration statement should be specified with the *enable* parameter.

Appendix A. Links

- **The Hercules System/370, ESA/390, and z/Architecture Emulator**
<http://www.hercules-390.org>
- **Hercules Developer Snapshots (Ivan Warren)**
<http://www.ivansoftware.com/snapshots/snapshots>
- **Hercules PDF Documentation (Peter Glanzmann)**
<http://hercdoc.glanzmann.org>
- **The MVS Tur(n)key System, Version 3 (Volker Bandke)**
<http://www.bsp-gmbh.com/turnkey/index.html>
<http://www.mvs-turnkey.de>
- **Hercules WinGUI (“Fish”, David B. Trout)**
<http://www.softdevlabs.com/Hercules/hercgui-index.html>
- **CTCI-W32 (“Fish”, David B. Trout)**
<http://www.softdevlabs.com/Hercules/ctci-w32-index.html>
- **Hercules Studio (Jacob Dekel)**
<http://www.mvsdasd.org/hercstudio>
- **WinPcap, Politecnico di Torino**
<http://www.winpcap.org>

- **Vista tn3270, Tom Brennan Software**
<http://www.tombrennansoftware.com>
- **X3270, Paul Mattes**
<http://x3270.bgp.nu>
- **AWSBROWSE (“Fish”, David B. Trout)**
<http://www.softdevlabs.com/Hercules/hercgui-index.html>
- **XMIT Manager**
www.cbttape.org
- **CBT MVS Utilities Tape (CBTTAPE)**
www.cbttape.org
- **Microsoft Visual C++ 2008 Express**
<http://www.microsoft.com/express/download/>
- **ZLIB**
<http://www.zlib.net>
<http://www.softdevlabs.com/Hercules/ZLIB1-1.2.3-bin-lib-inc-vc2008-x86-x64.zip>
- **BZIP2**
<http://www.bzip.org>
<http://www.softdevlabs.com/Hercules/BZIP2-1.0.5-bin-lib-inc-vc2008-x86-x64.zip>

- **PCRE**

<http://www.pcre.org>

<http://www.softdevlabs.com/Hercules/PCRE-6.4.1-bin-lib-inc-vc2008-x86-x64.zip>

Index

A

Acknowledgements 8
Action..... 12

C

Card Punch Emulation 11, 156
Card Reader Emulation 12, 157
Channel-to-Channel Adapter Emulation 11, 49
Communication Adapter Emulation 11, 16
Configuration File Processing 11, 24
console 10
Control Panel Command Messages 147
copyright notices 7
CPU Emulation 11, 44

D

DASD Emulation 11, 59
DASD Utilities Common Functions 11, 105
DASDCAT Utility 11, 103
DASDCOPY Utility 11, 60
DASDINIT Utility 11, 65
DASDISUP Utility 11, 98
DASDLOAD Utility 11, 66
Debug 12
Dyngui.DLL 11, 63

E

Error 12

F

Function List 10, 12
 Card Punch Emulation 11, 156
 Card Reader Emulation 12, 157
 Channel-to-Channel Adapter Emulation 11, 49
 Communication Adapter Emulation 11, 16
 Configuration File Processing 11, 24
 Control Panel Command Messages 147
 CPU Emulation 11, 44
 DASD Emulation 11, 59
 DASD Utilities Common Functions 11, 105
 DASDCAT Utility 11, 103
 DASDCOPY Utility 11, 60
 DASDINIT Utility 11, 65
 DASDISUP Utility 11, 98
 DASDLOAD Utility 11, 66
 Dyngui.DLL 11, 63
 hercfc 133
 Hercules Control Panel Command Messages 11
 Hercules Dynamic Loader 11, 121
 Hercules Initialization 11, 135
 HETGET Utility 11, 127
 HETINIT Utility 11, 126
 HETMAP Utility 11, 128
 HETUPD Utility 11, 132

HTTP Server 11, 129
LCS Emulation 11, 138
Network Interface Configuration Handler .. 11, 133
Printer Emulation 11, 153
Socket Devices Common Functions 12, 162
System Log Functions 11, 144
Tape Device Emulation 12, 163
TAPECOPY Utility 12, 164
TAPEMAP Utility 12, 169
TAPESPLT Utility 12, 170
Terminal Emulation 12, 165
TOD Clock and Timer Services 12, 171
TUN / TAP Driver Support 12, 172

G

General Information 9

H

hercfc 11, 133
Hercules Control Panel Command Messages 11
Hercules Dynamic Loader 11, 121
Hercules Initialization 11, 135
Hercules Release 6
HETGET Utility 11, 127
HETINIT Utility 11, 126
HETMAP Utility 11, 128
HETUPD Utility 11, 132
HHCAOnnns 15
HHCCAAnnns 16
 HHCCA001I 16
 HHCCA002I 16
 HHCCA003E 16
 HHCCA004W 17
 HHCCA005I 17
 HHCCA006T 17
 HHCCA007W 18
 HHCCA008I 18
 HHCCA009I 18
 HHCCA010I 19
 HHCCA011E 19
 HHCCA012E 19
 HHCCA013E 20
 HHCCA014E 20
 HHCCA015E 20
 HHCCA016W 21
 HHCCA017I 21
 HHCCA018E 21
 HHCCA019E 22
 HHCCA020E 22
 HHCCA021I 22
 HHCCA300D 23
HHCCFnnns 24
 HHCCF001S 24
 HHCCF002S 24
 HHCCF003S 24

HHCCF004S	24	HHCCF064W	38
HHCCF005S	25	HHCCF065I	39
HHCCF006S	25	HHCCF066E	39
HHCCF007S	25	HHCCF067S	39
HHCCF008E	25	HHCCF068E	39
HHCCF009S	26	HHCCF069I	40
HHCCF010S	26	HHCCF074E	40
HHCCF011S	26	HHCCF075E	40
HHCCF012S	26	HHCCF076E	40
HHCCF013S	27	HHCCF077E	41
HHCCF014S	27	HHCCF079A	41
HHCCF015S	27	HHCCF081I	41
HHCCF016S	27	HHCCF082S	42
HHCCF017W	28	HHCCF083I	42
HHCCF018S	28	HHCCF084W	41, 42
HHCCF019S	28	HHCCF085S	41, 42
HHCCF020W	28	HHCCF086S	43
HHCCF021S	29	HHCCF089S	43
HHCCF022S	29	HHCCPnnns	44
HHCCF023S	29	HHCCP001W	44
HHCCF024S	29	HHCCP002I	44
HHCCF025S	30	HHCCP003I	44
HHCCF026S	30	HHCCP004I	44
HHCCF027S	30	HHCCP005E	45
HHCCF028S	30	HHCCP006S	45
HHCCF029S	31	HHCCP007I	45
HHCCF030S	31	HHCCP008I	45
HHCCF031S	31	HHCCP009E	46
HHCCF032S	31	HHCCP010I	46
HHCCF033S	32	HHCCP011I	46
HHCCF034W	32	HHCCP023I	46
HHCCF035S	32	HHCCP024I	47
HHCCF036S	32	HHCCP025I	47
HHCCF037S	33	HHCCP026I	47
HHCCF038S	33	HHCCP027I	47
HHCCF039W	33	HHCCP090W	48
HHCCF040E	33	HHCCTnnns	49
HHCCF041E	34	HHCCUnnns	50
HHCCF042E	34	HHCCU101I	50
HHCCF043E	34	HHCCU102I	50
HHCCF044E	34	HHCCU103I	50
HHCCF045E	35	HHCCU104I	51
HHCCF046E	35	HHCCU300I	51
HHCCF047I	35	HHCCU301I	51
HHCCF048E	35	HHCCU500W	51
HHCCF049E	35	HHCCU501W	51
HHCCF050I	36	HHCCU502W	52
HHCCF051S	36	HHCCU600W	52
HHCCF052S	36	HHCCU601W	52
HHCCF053E	36	HHCCU602W	52
HHCCF054E	37	HHCCU603W	53
HHCCF055E	37	HHCCU604W	53
HHCCF056E	37	HHCCU610W	53
HHCCF057E	37	HHCCU620W	53
HHCCF058E	37	HHCCU621W	54
HHCCF061W	38	HHCCU622W	54
HHCCF062W	38	HHCCU700E	54
HHCCF063W	38	HHCCU701E	54

HHCCU702E	55	HHCDL020E	70
HHCCU703E	55	HHCDL021E	71
HHCCU704E	55	HHCDL022E	71
HHCCU705E	55	HHCDL023E	71
HHCCU706E	56	HHCDL024E	71
HHCCU707E	56	HHCDL025E	72
HHCCU708E	56	HHCDL026E	72
HHCCU900E	56	HHCDL027E	72
HHCCU901E	56	HHCDL028E	72
HHCCU902E	57	HHCDL029E	72
HHCCU903E	57	HHCDL030E	73
HHCCU904E	57	HHCDL031E	73
HHCCU905E	57	HHCDL032E	73
HHCCU910E	58	HHCDL033E	73
HHCCU999E	58	HHCDL034E	73
HHCDAnnns	59	HHCDL035E	74
HHCDCnns	60	HHCDL036E	74
HHCDC001E	60	HHCDL037I	74
HHCDC002E	60	HHCDL038E	74
HHCDC003E	60	HHCDL039E	75
HHCDC004E	60	HHCDL040E	75
HHCDC005E	61	HHCDL041E	75
HHCDC006E	61	HHCDL042E	75
HHCDC007E	61	HHCDL043E	76
HHCDC008E	61	HHCDL044E	76
HHCDC009E	62	HHCDL045E	76
HHCDC010I	62	HHCDL046E	76
HHCDGnns	63	HHCDL047E	77
HHCDG001I	63	HHCDL048I	77
HHCDG002I	63	HHCDL049E	77
HHCDG003S	63	HHCDL050E	77
HHCDG004S	63	HHCDL051E	78
HHCDG005E	63	HHCDL052E	78
HHCDG006S	64	HHCDL053E	78
HHCDG007S	64	HHCDL054E	78
HHCDInns	65	HHCDL055E	79
HHCDI001I	65	HHCDL056E	79
HHCDI002I	65	HHCDL057I	79
HHCDLnns	66	HHCDL058I	79
HHCDL001E	66	HHCDL059I	80
HHCDL002E	66	HHCDL060E	80
HHCDL003E	66	HHCDL061E	80
HHCDL004E	66	HHCDL062I	80
HHCDL005E	67	HHCDL063E	81
HHCDL006I	67	HHCDL064E	81
HHCDL007E	67	HHCDL065E	81
HHCDL008E	67	HHCDL066E	81
HHCDL009I	68	HHCDL067E	81
HHCDL010E	68	HHCDL068E	82
HHCDL011E	68	HHCDL069E	82
HHCDL012I	68	HHCDL070E	82
HHCDL013I	69	HHCDL071E	82
HHCDL014I	69	HHCDL072E	83
HHCDL015W	69	HHCDL073E	83
HHCDL016I	69	HHCDL074E	83
HHCDL017I	70	HHCDL075E	83
HHCDL018E	70	HHCDL076I	84
HHCDL019E	70	HHCDL077E	84

HHCDL078I	84	HHCDS007W	99
HHCDL079I	84	HHCDS008W	99
HHCDL080E	85	HHCDS009I	100
HHCDL081E	85	HHCDS010I	100
HHCDL082E	85	HHCDS011E	99, 100
HHCDL083E	85	HHCDS012E	100
HHCDL084I	86	HHCDS013I	101
HHCDL085I	86	HHCDS014E	101
HHCDL086I	86	HHCDS015E	101
HHCDL087E	86	HHCDS016E	101
HHCDL088E	87	HHCDS017E	102
HHCDL089I	87	HHCDS018I	102
HHCDL090I	87	HHCDS019I	102
HHCDL091E	87	HHCDTnnns	103
HHCDL092E	88	HHCDT001E	103
HHCDL093E	88	HHCDT002E	103
HHCDL094E	88	HHCDT003E	103
HHCDL095I	88	HHCDT004E	103
HHCDL096I	89	HHCDT005E	104
HHCDL097E	89	HHCDUnnns	105
HHCDL098I	89	HHCDU001I	105
HHCDL099E	89	HHCDU002E	105
HHCDL100E	90	HHCDU003I	105
HHCDL101E	90	HHCDU004E	105
HHCDL102E	90	HHCDU005I	106
HHCDL103E	90	HHCDU006I	106
HHCDL104I	91	HHCDU007E	106
HHCDL105E	91	HHCDU008E	106
HHCDL106E	91	HHCDU009E	107
HHCDL107E	91	HHCDU010E	107
HHCDL108E	92	HHCDU011E	107
HHCDL109E	92	HHCDU012E	107
HHCDL110I	92	HHCDU013E	108
HHCDL111I	92	HHCDU014I	108
HHCDL112I	93	HHCDU015I	108
HHCDL113I	93	HHCDU016E	108
HHCDL114E	93	HHCDU017E	109
HHCDL115I	93	HHCDU018E	109
HHCDL116E	94	HHCDU019E	109
HHCDL117I	94	HHCDU020I	109
HHCDL118I	94	HHCDU021E	110
HHCDL119I	94	HHCDU022I	110
HHCDL120I	95	HHCDU023I	110
HHCDL121E	95	HHCDU024E	110
HHCDL122E	95	HHCDU025I	110
HHCDL123E	95	HHCDU026E	111
HHCDL124E	96	HHCDU027E	111
HHCDL125E	96	HHCDU028E	111
HHCDL126E	96	HHCDU029E	111
HHCDL127E	96	HHCDU030E	112
HHCDL128E	97	HHCDU031E	112
HHCDSnnns	98	HHCDU032E	112
HHCDS001E	98	HHCDU033E	112
HHCDS002I	98	HHCDU034E	112
HHCDS003E	98	HHCDU035E	113
HHCDS004E	98	HHCDU036E	113
HHCDS005E	99	HHCDU037E	113
HHCDS006W	99, 100	HHCDU038E	113

HHCDU039E.....	114	HHCHT004E.....	129
HHCDU040E.....	114	HHCHT005E.....	130
HHCDU041I.....	114	HHCHT006I.....	130
HHCDU042E.....	114	HHCHT007E.....	130
HHCDU043E.....	114	HHCHT008E.....	130
HHCDU044I.....	115	HHCHT009E.....	130
HHCDU045E.....	115	HHCHT010E.....	131
HHCDU046E.....	115	HHCHT011E.....	131
HHCDU047I.....	115	HHCHT014I.....	131
HHCDU048E.....	116	HHCHUnnns.....	132
HHCDU049E.....	116	HHCIFnnns	
HHCDU050E.....	116	HHCIF001E.....	133
HHCDU051E.....	116	HHCIF002E.....	133
HHCDU052I.....	116	HHCIF003E.....	133
HHCDU053E.....	117	HHCIF004W.....	133
HHCDU054E.....	117	HHCIF005E.....	134
HHCDU055I.....	117	HHCINnnns.....	135
HHCDU056E.....	117	HHCIN001S.....	135
HHCDU057E.....	118	HHCIN002E.....	135
HHCDU058E.....	118	HHCIN003S.....	135
HHCDU059E.....	118	HHCIN004S.....	135
HHCDU060E.....	118	HHCIN005S.....	136
HHCDU061E.....	119	HHCIN006S.....	136
HHCDU062E.....	119	HHCIN007S.....	136
HHCDU063E.....	119	HHCIN008S.....	136
HHCDU064E.....	119	HHCIN099I.....	137
HHCDU065E.....	120	HHCLCnnns.....	138
HHCDU066E.....	120	HHCLC001E.....	138
HHCDU067E.....	120	HHCLC017E.....	138
HHCDU068I.....	120	HHCLC018E.....	138
HHCHDnnns.....	121	HHCLC019E.....	138
HHCHD001E.....	121	HHCLC020E.....	139
HHCHD002E.....	121	HHCLC021E.....	139
HHCHD003E.....	121	HHCLC022E.....	139
HHCHD004I.....	121	HHCLC023E.....	139
HHCHD005E.....	122	HHCLC024E.....	139
HHCHD006S.....	122	HHCLC025E.....	140
HHCHD007E.....	122, 136	HHCLC026E.....	140
HHCHD008I.....	122	HHCLC027E.....	140
HHCHD009E.....	122	HHCLC028E.....	140
HHCHD010I.....	123, 124	HHCLC029E.....	140
HHCHD011I.....	123, 124	HHCLC031E.....	141
HHCHD012E.....	123	HHCLC032E.....	141
HHCHD013E.....	123	HHCLC033E.....	141
HHCHD014E.....	124	HHCLC034E.....	141
HHCHD015E.....	124	HHCLC035E.....	141
HHCHD018I.....	124	HHCLC036E.....	142
HHCHD100I.....	124	HHCLC037E.....	142
HHCHD101I.....	124	HHCLC038E.....	142
HHCHD102I.....	125	HHCLC039E.....	142
HHCHD103I.....	125	HHCLC040E.....	142
HHCHEnnns.....	126	HHCLC055I.....	143
HHCHGnnns.....	127	HHCLC056W.....	143
HHCHMnnns.....	128	HHCLC073I.....	143
HHCHTnnns.....	129	HHCLGnnns.....	144
HHCHT001I.....	129	HHCLG001E.....	144
HHCHT002E.....	129	HHCLG002E.....	144
HHCHT003W.....	129	HHCLG003E.....	144

HHCLG004E	144	HHCRD006E	158
HHCLG005E	144	HHCRD007I	158
HHCLG006E	144	HHCRD008W	158
HHCLG007S	145	HHCRD009E	159
HHCLG008S	145	HHCRD010E	159
HHCLG009S	145	HHCRD011E	159
HHCLG012E	145	HHCRD012I	159
HHCLG014E	145	HHCRD013E	159
HHCLG015I	146	HHCRD014E	160
HHCLG016E	146	HHCRD015E	160
HHCLG017S	146	HHCRD016E	160
HHCLG018I	146	HHCRD017E	160
HHCPNnnns	147	HHCRD018E	161
HHCPN001I	147	HHCRD019E	161
HHCPN002S	147	HHCSDnnns	162
HHCPN003S	147	HHCTAnnns	163
HHCPN004E	147	HHCTCnnns	164
HHCPN005E	148	HHCTEnnns	165
HHCPN006E	148	HHCTE001I	165
HHCPN007E	148	HHCTE002W	165
HHCPN008I	148	HHCTE003I	165
HHCPN009E	149	HHCTE004I	165
HHCPN010W	149	HHCTE005E	166
HHCPN011I	149	HHCTE006A	166
HHCPN012I	149	HHCTE007I	166
HHCPN013I	150	HHCTE008I	166
HHCPN014E	150	HHCTE009I	167
HHCPN052E	150	HHCTE010E	167
HHCPN162I	150	HHCTE011E	167
HHCPN180E	151	HHCTE012E	167
HHCPN181E	151	HHCTE013E	167
HHCPN195I	151	HHCTE014I	168
HHCPN196E	151	HHCTE017E	168
HHCPN197I	152	HHCTMnnns	169
HHCPRnnns	153	HHCTSnnns	170
HHCPR001E	153	HHCTTnnns	171
HHCPR002E	153	HHCTT001W	171
HHCPR003E	153	HHCTT002I	171
HHCPR004E	153	HHCTT003I	171
HHCPR005E	154	HHCTUnnns	172
HHCPR006E	154	HHCVMnnns	173
HHCPR007I	154	HHCVM001I	173
HHCPR008E	154	HHCVM002I	173
HHCPR009E	155	HHCVM003I	173
HHCPR010E	155	HHCVM004E	174
HHCPR011I	155	HTTP Server	11, 129
HHCPR012E	155		
HHCPUnnns	156	I	
HHCPU001E	156	Information	12
HHCPU002E	156	Installation Guide	9
HHCPU003E	156		
HHCPU004E	156	L	
HHCRDnnns	157	LCS Emulation	11, 138
HHCRD001E	157	Legal Advice	7
HHCRD002E	157	Links	175
HHCRD003E	157	Locations	10
HHCRD004E	157		
HHCRD005E	158		

M

Message Examples	13
Message Format	10
message number	10
message prefix	10
message severity	10
message number	10
message prefix	10
message severity	10
Message Severity	12
Messages	
Locations	10
Messages and Codes	9

N

Network Interface Configuration Handler	11, 133
---	---------

P

Printer Emulation	11, 153
Publication Number	6
Publications	
General Information	9
Installation Guide	9
Messages and Codes	9
Reference Summary	9
User Reference Guide	9

R

Readers Comments	7
Reference Summary	9

Revision Notice

Hercules Release	6
Publication Number	6
Revision Number	6
SoftCopy Name	6
Revision Number	6

S

Sample Messages	14
Severe error	12
Socket Devices Common Functions	12, 162
SoftCopy Name	6
System Log Functions	11, 144

T


Tape Device Emulation	12, 163
TAPECOPY Utility	12, 164
TAPEMAP Utility	12, 169
TAPESPLT Utility	12, 170
Terminal Emulation	12, 165
TOD Clock and Timer Services	12, 171
Trademarks	7
TUN / TAP Driver Support	12, 172

U

User Reference Guide	9
----------------------------	---

W

Warning	12
Windows GUI	10

Hercules Emulator

<p data-bbox="676 949 735 1346">Hercules System/370, ESA/390, z/Architecture Emulator</p> <p data-bbox="807 882 863 1420">Messages and Codes</p> <p data-bbox="932 1016 959 1285">Version 3 Release 07</p>
HEMC030700-02